

1

2

3

4

Document Number: DSP1053

Date: 2009-12-11

Version: 1.0.1

Base Metrics Profile 5

Document Type: Specification 6

Document Status: DMTF Standard 7

8 **Document Language: E**

- 10 Copyright notice
- 11 | Copyright © 2009 Distributed Management Task Force, Inc. (DMTF). All rights reserved.
- 12 DMTF is a not-for-profit association of industry members dedicated to promoting enterprise and systems
- 13 management and interoperability. Members and non-members may reproduce DMTF specifications and
- 14 documents, provided that correct attribution is given. As DMTF specifications may be revised from time to
- time, the particular version and release date should always be noted.
- 16 Implementation of certain elements of this standard or proposed standard may be subject to third party
- 17 patent rights, including provisional patent rights (herein "patent rights"). DMTF makes no representations
- 18 to users of the standard as to the existence of such rights, and is not responsible to recognize, disclose,
- or identify any or all such third party patent right, owners or claimants, nor for any incomplete or
- 20 inaccurate identification or disclosure of such rights, owners or claimants. DMTF shall have no liability to
- any party, in any manner or circumstance, under any legal theory whatsoever, for failure to recognize,
- 22 disclose, or identify any such third party patent rights, or for such party's reliance on the standard or
- 23 incorporation thereof in its product, protocols or testing procedures. DMTF shall have no liability to any
- 24 party implementing such standard, whether such implementation is foreseeable or not, nor to any patent
- 25 owner or claimant, and shall have no liability or responsibility for costs or losses incurred if a standard is
- 26 withdrawn or modified after publication, and shall be indemnified and held harmless by any party
- 27 implementing the standard from any and all claims of infringement by a patent owner for such
- 28 implementations.
- 29 For information about patents held by third-parties which have notified the DMTF that, in their opinion,
- 30 such patent may relate to or impact implementations of DMTF standards, visit
- 31 http://www.dmtf.org/about/policies/disclosures.php.

32 CONTENTS

33	For	eword.		7
34	Intr	oductio	n	8
35	1		e	
36	2		ative References	
37	3		s and Definitions	
38	4	•	ools and Abbreviated Terms	
39	5		psis	
40	6		ription (Informative)	
41		6.1	Metric Access Types	
42		6.2	Metric Time Scope	
43		6.3	Metric Value Formulation	
44		6.4	Metric Context	
45	7	Imple	mentation	
46		7.1	Common Requirements	
47		7.2	Modeling Metric Access Types	
48		7.3	Modeling Metric Time Scope	
49		7.4	Modeling Metric Value Formulation	
50		7.5	Relationship between Aggregation and Base Metrics	
51		7.6	Constraints on Metric Values for Controllable Metrics	
52	8	Metho		
53		8.1	CIM_MetricService.ShowMetrics()	
54		8.2	CIM_MetricService.ShowMetricsByClass()	
55		8.3	CIM_MetricService.ControlMetrics()	
56		8.4	CIM_MetricService.ControlMetricsByClass()	
57		8.5	CIM_MetricService.GetMetricValues()	
58		8.6	Profile Conventions for Operations	
59		8.7	CIM_AggregationMetricDefinition	
60		8.8	CIM_AggregationMetricValue	
61		8.9	CIM_BaseMetricDefinition	
62		8.10	CIM_BaseMetricValue	
63		8.11	CIM_ConcreteDependency	
64		8.12	CIM_ElementCapabilities	
65		8.13	CIM_HostedService	
66		8.14	-	
67		8.15	-	
86		8.16	-	
69 70		8.17		
70 71		8.18	CIM_MetricServiceCapabilities	
71	_		CIM_ServiceAffectsElement	
72	9		Cases (Informative)	29
73		9.1	Instructions Executed per Second	
74		9.2	Object Diagram for Startup Interval Time Scope	
75		9.3	Metric Definition for Multiple Instances of CIM_ManagedElement	
76		9.4	Controllable Metrics	
77		9.5	Aggregation Metrics	
78 70		9.6	Metric Context	
79		9.7	Find All Metric Definitions for a Managed Element	
80 94		9.8	Find the Metric Value for a Managed Element	
81 82		9.9	Find a Standard Metric for a Managed Element Retrieve a Metric Value	
5∠ 33		9.10 9.11	Find All Metrics Available for a Managed Element within an Enumeration Scope	
JJ		9.11	Time All Methos Available for a Mahayed Liethetit Within all Enumeration 300pe	↔∪

84 85 86		 2 Find All Metrics Available within an Enumeration Scope for All Instances of a CIM Class 3 Determine whether a Metric Can Be Discretely Controlled for a Specific Managed Element 	
87	9.1		46
88	9.1	5 Find All Managed Elements within an Enumeration Scope for which a Metric Is Currently	
89		Being Collected	
90	10 CII	VI Elements	47
91	10.	.1 CIM_AggregationMetricDefinition	47
92	10.	.2 CIM_AggregationMetricDefinition (Low Watermark)	48
93	10.	.3 CIM_AggregationMetricDefinition (High Watermark)	48
94	10.	= 55 5	
95	10.	-	
96	10.	-	
97 98	10. 10.	.7 CIM_BaseMetricDefinition — Interval Metric	
99		9 CIM_BaseMetricDefinition — Startup Interval Metric	
100		.10 CIM BaseMetricDefinition — Current Data	
101		.11 CIM BaseMetricValue	
102		.12 CIM_BaseMetricValue — Current Data	
103		.13 CIM_BaseMetricValue — Interval Metrics	
104		.14 CIM_BaseMetricValue — Startup Interval Metrics	
105		.15 CIM_BaseMetricValue — Summation Metric	
106		.16 CIM_BaseMetricValue — Long-Term Monitoring	
107 108		.17 CIM_ConcreteDependency (Definition)	
108		.18 CIM_ConcreteDependency (Value)	
110		.20 CIM HostedService	
111		.21 CIM MetricDefForME	
112		.22 CIM_MetricForME	
113		.23 CIM_MetricInstance	
114		.24 CIM_MetricService	
115		.25 CIM_MetricServiceCapabilities	
116 117		.26 CIM_RegisteredProfile	
118		A (Informative) Change Log	
		B (Informative) Guide for Common Metrics	
119		\	
120	Bibliogr	aphy	/ 1
121 122	Figure	s	
123	-	I – Base Metrics Profile: Class Diagram	
124	•	2 – Interval Metrics	
125	Figure 3	3 - Instantaneous Counter	31
126	Figure 4	4 – Instantaneous Gauge	32
127	Figure 5	5 – Usage Example for Startup Interval Time Scope	33
128	Figure 6	6 - Common Metric Definition for Multiple Instances of CIM_ManagedElement	34
129	Figure 7	7 – Advertising Support for Discrete Controllable Metrics	35
130	Figure 8	3 – Discrete Controllable Metrics (Before Enable)	36
131	Figure 9	9 – Discrete Controllable Metrics (After Enable)	37
132	-	10 – Bulk Controllable Metrics by Definition	
133	-	I1 – Bulk Controllable Metrics by Managed Element	
134	_	12 – Bulk Controllable Metrics by Class	
135	-	I3 – Aggregation Metric without Base	
	9 4. 5		

136	Figure 14 – Aggregation Metric with Base	42
137	Figure 15 – Metric Context	43
138		
139	Tables	
140	Table 1 – Referenced Profiles	12
141	Table 2 – CIM_MetricService.ShowMetrics() Method: Return Code Values	20
142	Table 3 - CIM_MetricService.ShowMetrics() Method: Parameters	
143	Table 4 – CIM_MetricService.ShowMetricsByClass() Method: Return Code Values	
144	Table 5 - CIM_MetricService.ShowMetricsByClass() Method: Parameters	
145	Table 6 – CIM_MetricService.ControlMetrics() Method: Return Code Values	
146	Table 7 – CIM_MetricService.ControlMetrics() Method: Parameters	
147	Table 8 – CIM_MetricService.ControlMetricsByClass() Method: Return Code Values	
148	Table 9 – CIM_MetricService.ControlMetricsByClass() Method: Parameters	
149	Table 10 – CIM_MetricService.GetMetricValues() Method: Return Code Values	
150	Table 11 – CIM_MetricService.GetMetricValues() Method: Parameters	
151	Table 12 – Operations: CIM_ConcreteDependency	
152	Table 13 – Operations: CIM_ElementCapabilities	
153	Table 14 – Operations: CIM_HostedService	
154 155	Table 15 – Operations: CIM_MetricDefForME Table 16 – Operations: CIM MetricForME	
155 156	Table 17 – Operations: CIM_MetricForME	
157	Table 18 – Operations: CIM_ServiceAffectsElement	
158	Table 19 – CIM Elements: Base Metrics Profile	
159	Table 20 – Class: CIM_AggregationMetricDefinition	
160	Table 21 – Class: CIM_AggregationMetricDefinition (Low Watermark)	
161	Table 22 – Class: CIM_AggregationMetricDefinition (High Watermark)	
162	Table 23 – Class: CIM_AggregationMetricValue	
163	Table 24 – Class: CIM_BaseMetricDefinition	49
164	Table 25 – Class: CIM_BaseMetricDefinition – Instantaneous Metric	50
165	Table 26 - Class: CIM_BaseMetricDefinition - Interval Metric	50
166	Table 27 – Class: CIM_BaseMetricDefinition – Startup Interval Metric	50
167	Table 28 – Class: CIM_BaseMetricDefinition – Summation Metric	50
168	Table 29 - Class: CIM_BaseMetricDefinition - Current Data	51
169	Table 30 - Class: CIM_BaseMetricValue	
170	Table 31 - Class: CIM_BaseMetricValue - Current Data	
171	Table 32 – Class: CIM_BaseMetricValue – Interval Metrics	
172	Table 33 – Class: CIM_BaseMetricValue – Startup Interval Metrics	
173	Table 34 – Class: CIM_BaseMetricValue – Summation Metric	
174	Table 35 – Class: CIM_BaseMetricValue – Long-Term Monitoring	
175	Table 36 – Class: CIM_ConcreteDependency (Definition)	
176	Table 37 – Class: CIM_ConcreteDependency (Value)	
177 170	Table 38 – Class: CIM_ElementCapabilities	
178 179	Table 39 – Class: CIM_HostedService	
179 180	Table 41 – Class: CIM_MetricForME	
180 181	Table 41 – Class: CIM_MetricInstance	
182	Table 43 – Class: CIM_MetricService	
102	Table 40 Class. Clivi_IvietileCel vice	

	Base Metrics Profile	DSP1053
183	Table 44 – Class: CIM_MetricServiceCapabilities	55
184	Table 45 – Class: CIM_RegisteredProfile	56
185	Table 46 – Class: CIM_ServiceAffectsElement	56
186	Table B.1 – Simple Metric	59
187	Table B.2 – Summation Metric	61
188	Table B.3 – Aggregation Metric	63
189	Table B.4 – Aggregation Metric – Low Watermark	65
190	Table B.5 – Aggregation Metric – High Watermark	68

192	Foreword
193	The Base Metrics Profile (DSP1053) was prepared by the Applications Working Group of the DMTF.
194 195	DMTF is a not-for-profit association of industry members dedicated to promoting enterprise and systems management and interoperability.
196	Acknowledgments
197	The authors wish to acknowledge the following people.
198	Editors:
199	Oliver Benke – IBM
200	Aaron Merkin – IBM
201	Khachatur Papanyan – Dell
202	Contributors:
203	Andreas Maier — IBM
204	Karl Schopmeyer – The Open Group

205	Introduction
206 207 208	The information in this specification should be sufficient for a provider or consumer of this data to identify unambiguously the classes, properties, methods, and values that shall be instantiated and manipulated to represent and manage the components described in this document.
209 210 211	The target audience for this specification is implementers who are writing Common Information Model (CIM)-based providers or consumers of management interfaces that need to dynamically add metrics to existing components.

Base Metrics Profile

212

213	1 Scope	
214 215 216 217	The Base Metrics Profile is a component profile that defines the minimum object model needed to dynamic metrics associated to existing managed elements and related associations. This profile document how to model metrics for capacity planning or accounting purposes. These topics are counting the Capacity Metrics Profile (DSP1073), which is a specialization of this profile.	oes not
218	2 Normative References	
219 220 221	The following referenced documents are indispensable for the application of this document. For dareferences, only the edition cited applies. For undated references, the latest edition of the reference document (including any amendments) applies.	
222 223	DMTF DSP0004, CIM Infrastructure Specification 2.3, http://www.dmtf.org/standards/published_documents/DSP0004_2.3.pdf	
224 225	DMTF DSP0200, CIM Operations over HTTP 1.2, http://www.dmtf.org/standards/published_documents/DSP0200_1.2.pdf	
226 227	DMTF DSP1001, Management Profile Specification Usage Guide 1.0, http://www.dmtf.org/standards/published_documents/DSP1001_1.0.pdf	
228 229	DMTF DSP1033, <i>Profile Registration Profile 1.0</i> , http://www.dmtf.org/standards/published_documents/DSP1033_1.0.pdf	
230 231	ISO/IEC Directives, Part 2, <i>Rules for the structure and drafting of International Standards</i> , http://isotc.iso.org/livelink/livelink.exe?func=ll&objId=4230456&objAction=browse&sort=subtype	
232	3 Terms and Definitions	
233	For the purposes of this document, the following terms and definitions apply.	
234 235	3.1 can	
236	used for statements of possibility and capability, whether material, physical, or causal	
237	3.2	
238 239	cannot used for statements of possibility and capability, whether material, physical, or causal	
240	3.3	
241	conditional	1
242 243	indicates requirements to be followed strictly in order to conform to the document when the specific conditions are met	ed

- 244 **3.4**
- 245 mandatory
- 246 indicates requirements to be followed strictly in order to conform to the document and from which no
- 247 deviation is permitted
- 248 **3.5**
- 249 may
- indicates a course of action permissible within the limits of the document
- 251 **3.6**
- 252 need not
- 253 indicates a course of action permissible within the limits of the document
- 254 **3.7**
- 255 optional
- 256 indicates a course of action permissible within the limits of the document
- 257 **3.8**
- 258 referencing profile
- 259 indicates a profile that owns the definition of this class and can include a reference to this profile in its
- 260 "Referenced Profiles" table
- 261 **3.9**
- 262 shall
- 263 indicates requirements to be followed strictly in order to conform to the document and from which no
- 264 deviation is permitted
- 265 **3.10**
- 266 shall not
- 267 indicates requirements to be followed in order to conform to the document and from which no deviation is
- 268 permitted
- 269 **3.11**
- 270 should
- 271 indicates that among several possibilities, one is recommended as particularly suitable, without
- 272 mentioning or excluding others, or that a certain course of action is preferred but not necessarily required
- 273 **3.12**
- 274 should not
- 275 indicates that a certain possibility or course of action is deprecated but not prohibited
- 276 **3.13**
- 277 unspecified
- 278 indicates that this profile does not define any constraints for the referenced CIM element or operation
- 279 **3.14**
- 280 aggregation metric
- a type of metric that is derived by applying a formula or filter to a set of base metric values
- 282 **3.15**
- 283 base metric
- a metric provided directly without a dependency on other metric values

- 285 **3.16**
- 286 measured resource
- a managed object being measured, which is the resource to which base metric value instances are
- 288 associated
- 289 **3.17**
- 290 sampling interval
- a value that determines how often new metric values are retrieved, if metrics are retrieved periodically
- 292 **3.18**
- 293 current data
- the most current data available for a given metric. Online monitoring (3.19) and snapshot monitoring
- 295 (3.20) are types of current data access.
- 296 **3.19**
- 297 online monitoring
- 298 the process in which metric values (typically interval metrics) are gathered asynchronously to a request
- 299 from the instrumentation or reporting layer
- 300 **3.20**
- 301 snapshot monitoring
- 302 the process in which metric values are gathered synchronously with a request from the instrumentation or
- 303 reporting layer
- 304 **3.21**
- 305 long-term monitoring
- 306 the process in which metric values are captured during an interval
- 307 **3.22**
- 308 event-based monitoring
- 309 the process in which threshold values for metrics are used to trigger asynchronous notification
- 310 **3.23**
- 311 instantaneous metrics
- 312 metrics that apply to a particular point in time. An example of an instantaneous metric is the amount of
- 313 memory currently allocated to a virtual server.
- 314 **3.24**
- 315 interval metrics
- 316 metrics that apply to a time interval. An example of an interval metric is the average CPU utilization of a
- 317 server over the past hour.
- 318 **3.25**
- 319 summation metrics
- 320 a type of counter metric that reflects the accumulation of a value
- 321 **3.26**
- 322 watermark metrics
- 323 a type of aggregation metric used to capture the minimum or maximum value recorded for a monitored
- 324 value

4 Symbols and Abbreviated Terms

326 **4.1**

325

327 **CPU**

328 central processing unit

329 **4.2**

330 **IEPS**

331 instructions executed per second

332 **4.3**

333 UTC

334 Universal Time Coordinated

335 4.4

336 **UUID**

337 Universally Unique Identifier

338 5 Synopsis

339 **Profile Name:** Base Metrics

340 Version: 1.0.1

341 Organization: DMTF

342 CIM Schema Version: 2.23

343 Central Class: CIM MetricService

344 Scoping Class: CIM_System

Table 1 identifies profiles on which this profile has a dependency.

346 Table 1 – Referenced Profiles


Profile Name	Organization	Version	Relationship	Behavior
Profile Registration	DMTF	1.0	Mandatory	

347 6 Description (Informative)

348 The Metrics Model provides the ability to model and control metrics captured for managed elements.

Figure 1 represents the class schema for the Base Metrics Profile. For simplicity, the prefix CIM_ has

350 been removed from the names of the classes.



351

352

353

354

355

356 357

358

359 360

362

365

366

367 368

369

370

371

372

373

374

375

Figure 1 – Base Metrics Profile: Class Diagram

A metric instance is represented by an instance of CIM_BaseMetricValue or its subclass CIM_AggregationMetricValue. The definition of the metric is provided by an associated instance of CIM_BaseMetricDefinition or CIM_AggregationMetricDefinition. The context of the metric is provided by one or more associated instances of CIM_ManagedElement. For example, an instance of CIM_ManagedElement could represent an operating system, a cluster, or a complex software application containing application server and database server parts. The modeling of the associated resources is out of the scope of this profile.

When defining a metric, there are four main characteristics to consider:

- Metric access type
 - Time scope of the metric
- Formulation of the metric value
- Metric context

These characteristics are described in the following sections. Some of these characteristics are modeled as attributes of an instance of CIM_BaseMetricDefinition. Others are modeled through the relationship of an instance of CIM_BaseMetricDefinition or CIM_BaseMetricValue to one or more instances of CIM_ManagedElement.

6.1 Metric Access Types

- There are three major access types for metrics and performance data:
 - Current data access, for data gathered in the recent past
- Long-term monitoring, for historical time series data
- Event-based monitoring, for asynchronous indication subscriptions based on instances of CIM_BaseMetricValue

6.1.1 Current Data

Current data access is the most common access type for dynamic metrics. The purpose is to request the most current data available to the implementation. There are two paradigms for the gathering metrics with an access type of current data, online monitoring and snapshot monitoring.

For the current data access type, CIM_BaseMetricValue.Volatile is equal to TRUE. The metric value

property is updated at the point in time that the instance is read.

381 **6.1.1.1 Online Monitoring**

- For the online monitoring access type, the CIM metric values are updated independently by the gathering
- infrastructure. When a new metric value is requested, the most current value is presented. Typically, the
- implementation of the gathering and reporting components can be separated. It is recommended to
- 385 synchronize metric retrieval in order to allow for correlation of various metrics. For the online monitoring
- access type, the value of the CIM_BaseMetricDefinition.GatheringType property is 3 (Periodic) or 2
- 387 (OnChange).

389

388 A well known UNIX application that implements this access type is "top".

6.1.1.2 Snapshot Monitoring

- 390 For the snapshot monitoring access type, the CIM metric value is determined each time a client
- 391 application requests a new metric value. The value of the CIM BaseMetricDefinition.GatheringType
- 392 property is 4 (OnRequest).
- Note that this access type has disadvantages. For example, data generated by snapshot monitoring is not
- 394 always suitable for event correlation. However, for simple investigations of the current state of the system,
- 395 snapshot monitoring is suitable, and it has the advantage that the gathering infrastructure needs to be
- 396 active only on request rather than continuously.
- 397 A well known UNIX application that implements this access type is "ps".

398 6.1.2 Long-Term Monitoring

- The long-term monitoring access type is used for historical time series. For example, it could be used to
- 400 collect all metric values gathered between 9:00 A.M. and 5:00 P.M. with 15 minute intervals.
- 401 For the long-term monitoring access type, the value of the CIM BaseMetricValue.Volatile property is
- 402 FALSE. The metric value is stored in a repository and can be retrieved by client applications later on.
- 403 A well known UNIX application that implements this access type is "sar/sadc".
- 404 Important aspects of the long-term monitoring access type are described in the Capacity Metrics Profile
- 405 (DSP1073).

406 **6.1.3 Event-Based Monitoring**

- The event-based monitoring access type is used for asynchronous indication subscriptions based on
- 408 base metric value instances, which allows the client to subscribe for certain threshold conditions. This
- 409 may be implemented based on CIM InstModification subscriptions for CIM BaseMetricValue changes.
- 410 Details on how to use event-based monitoring with dynamic metrics are out of the scope of this
- 411 document.

412

6.2 Metric Time Scope

- 413 Many common types of metrics can be captured. Metrics may be quantified along two axes. The first axis
- 414 is the time scope, and the second axis is the type of value formulation. Along the time scope axis, metrics
- 415 can be described as instantaneous, interval, or startup interval. Types of values captured include
- 416 minimum, maximum, average, instantaneous, and aggregate values.

417 6.2.1 Instantaneous Metrics

418 Instantaneous metrics report a monitored value at a given instant. An example of an instantaneous metric

- 419 is the amount of power being consumed by a system at a given point in time. For instantaneous metrics,
- 420 the value of the CIM BaseMetricDefinition.TimeScope property is 2 (Point).

421 6.2.2 Interval Metrics

- 422 Interval metrics are metrics captured over an interval in time. Interval metrics can report values such as
- 423 the average utilization of a resource over a period of time. An example of an ilnterval metric is the
- 424 average power consumption of a server over the last three days. For interval metrics, the value of the
- 425 CIM_BaseMetricDefinition.TimeScope property is 3 (Interval).

426 6.2.3 Startup Interval Metrics

- 427 Startup interval metrics are metrics captured over an interval in time, for which the start of the interval is
- 428 tied to a lifecycle change (initialization or creation) of the managed element for which the value is
- 429 captured. An example of a startup interval metric is the total number of CPU cycles consumed for a
- 430 transaction that is recorded from the time the transaction begins.

431 **6.3 Metric Value Formulation**

- 432 A metric's value may be constructed in innumerable ways. Three common types of metrics are simple
- 433 metrics, summation metrics, and aggregation metrics. These types are described in more detail in the
- 434 following clauses.

435 **6.3.1 Simple Metrics**

- Simple metrics report status recorded at some point in time without requiring a calculation or function to
- be applied to produce the value. An example of a simple metric is an instantaneous reading of the power
- 438 being consumed by a server.

439 **6.3.2 Summation Metrics**

- 440 Summation metrics are used to report aggregate or total values for a monitored entity. Uses of summation
- 441 metrics include billing, accounting, and capacity planning. An example of a summation metric is the total
- power consumed by a server for the last three days.
- 443 More information on using summation metrics is specified in DSP1073.

444 6.3.3 Aggregation Metrics

- 445 Aggregation metrics are metrics derived by applying a formula or filter to a set of base metric values.
- Aggregation metrics that apply a formula to metric values of multiple types are out of scope of this profile.
- The definition of an aggregation metric is provided by an instance of CIM_AggregationMetricDefinition. An
- aggregation metric includes the definition of a base metric as well as the function used to create the
- derived value. A server-side implementation may support the collection of an aggregation metric without
- 450 supporting the collection of the base metric. If collection of the base metric is supported, a distinct
- 451 instance of CIM BaseMetricDefinition is used to define the base metric and distinct instances of
- 452 CIM BaseMetricValue are used to represent the metric value. The CIM BaseMetricDefinition instance
- 453 may be associated to the CIM_AggregationMetricDefinition instance, and the CIM_BaseMetricValue
- instance may be associated with the CIM AggregationMetricValue instance.

Version 1.0.1 DMTF Standard 15

455 6.3.3.1 Watermark Metrics

Watermark metrics are a class of aggregation metrics. A watermark metric captures the highest or lowest

- 457 value recorded for a monitored entity. An example of a high watermark metric is the peak instantaneous
- 458 power consumed by a server in the past hour.

6.4 Metric Context

459

- 460 Generally it is necessary to understand the context of a metric in order to properly interpret and utilize the
- 461 reported values. An example is a metric that reports the number of packet errors per minute. If the metric
- 462 is reported for a single network interface, a much lower value is a cause for concern than if the metric is
- for an entire network segment.
- The CIM_MetricForME and CIM_MetricDefForME associations are used to provide the context in which a
- 465 metric is captured. CIM_MetricDefForME associates an instance of CIM_BaseMetricDefinition with an
- 466 instance of CIM ManagedElement. This indicates that the metric defined by the
- 467 CIM_BaseMetricDefinition can be captured for the resource modeled with the instance of
- 468 CIM_ManagedElement. The same metric can be available for multiple instances of
- 469 CIM_ManagedElement simultaneously. Therefore, it is necessary to further disambiguate the specific
- 470 instance of CIM_ManagedElement for which a particular instance of the metric has been captured. The
- 471 CIM MetricForME association is used to associate an instance of CIM BaseMetricValue with the
- instances of CIM_ManagedElement that provide its context.
- 473 A given defined metric may have multiple values available concurrently for a CIM_ManagedElement
- 474 instance. The BreakdownValue and BreakdownDimension properties are used to differentiate among the
- 475 instances of CIM_BaseMetricValue that provide multiple concurrent metric values for a
- 476 CIM_ManagedElement. An example of when multiple metric values for the same metric definition may be
- available is when a total value and values per component exist.

478 **7 Implementation**

- This section details the requirements related to the arrangement of instances and their properties for
- implementations of this profile.

481 **7.1 Common Requirements**

- 482 This section details the common requirements for modeling metrics. The requirements stated in this
- 483 section for the CIM BaseMetricDefinition and CIM BaseMetricValue classes shall also apply to the
- 484 CIM_AggregationMetricDefinition and CIM_AggregationMetricValue subclasses, respectively.

485 7.1.1 Service and Capabilities

- 486 At least one instance of CIM_MetricService shall exist. Each instance of CIM_MetricService shall be
- 487 associated with exactly one instance of CIM_System through the CIM_HostedService association. Each
- 488 instance of CIM MetricService shall be associated with exactly one instance of
- 489 CIM_MetricServiceCapabilities through the CIM_ElementCapabilities association. Each instance of
- 490 CIM BaseMetricDefinition shall be associated with exactly one instance of CIM MetricService through
- 491 the CIM ServiceAffectsElement association.

492 7.1.2 Relating a Metric Definition and Metric Value

- 493 Each instance of CIM BaseMetricValue shall be associated with exactly one instance of
- 494 CIM_BaseMetricDefinition through the CIM_MetricInstance association.
- 495 Each instance of CIM AggregationMetricValue shall be associated with exactly one instance of
- 496 CIM_AggregationMetricDefinition through the CIM_MetricInstance association.

497 **7.1.3** Identifying a Metric Definition

Incorporating profiles may specify metric definitions for metrics that are applicable to the management domain of the incorporating profile.

If the incorporating profile is a DMTF Management Profile, the CIM_BaseMetricDefinition.Name shall be formatted as follows:

502 "DMTF:<unique identifier> "

If the incorporating profile is not a DMTF Management Profile, the CIM_BaseMetricDefinition.Name property shall be formatted as follows:

< OrgID > : < LocalID >, where < OrgID > and < LocalID > are separated by a colon (:) and
 < OrgID > shall include a copyrighted, trademarked, or otherwise unique name that is owned by the
 business entity that is creating or defining the value or that is a registered ID assigned to the
 business entity by a recognized global authority. In addition, to ensure uniqueness, < OrgID > shall
 not contain a colon (:). If this algorithm is used, the first colon to appear in the value shall appear
 between < OrgID > and < LocalID > . < LocalID > is chosen by the business entity and shall be used
 uniquely.

512 **7.1.4 Identifying Metric Context**

513 The considerations for identifying the context of a metric are provided in the following sections.

7.1.4.1 General Requirements

- 515 Each instance of CIM_BaseMetricDefinition shall be associated with at least one instance of
- 516 CIM_ManagedElement through the CIM_MetricDefForME association. If the CIM_BaseMetricValue
- 517 instance models a metric with the current data access type, the CIM_BaseMetricValue instance shall be
- 518 associated with exactly one instance of CIM ManagedElement through the CIM MetricForME
- 519 association.

503

504

514

520 7.1.4.2 Breakdown Dimensions (Optional)

- 521 If multiple instances of CIM BaseMetricValue are available concurrently for a given instance of
- 522 CIM_ManagedElement, where the instances of CIM_BaseMetricValue are associated with the same
- 523 instance of CIM BaseMetricDefinition through instances of the CIM MetricValue association and the time
- frame for which the metric values are recorded overlaps in whole or in part, the requirements specified in
- 525 this subclause shall be met.
- The CIM_BaseMetricDefinition.BreakdownDimensions property shall not be NULL.
- 527 At most, one instance of CIM BaseMetricValue may have null values for the BreakdownDimension and
- 528 BreakdownValue properties.
- 529 If the incorporating profile that specifies the CIM BaseMetricDefinition is a DMTF Management Profile,
- and a value of the CIM_BaseMetricDefinition.BreakdownDimensions identifies a CIM class, the value
- 531 shall be formatted as:
- 532 <schemaName>"_"<simpleClassName>
- as specified in DSP0004.
- 534 If the incorporating profile that specifies the CIM BaseMetricDefinition is a DMTF Management Profile,
- and a value of the CIM BaseMetricDefinition.BreakdownDimensions does not identify a CIM class, the
- value shall be formatted as follows:
- 537 "DMTF" <unique identifier>

- If the incorporating profile is not a DMTF Management Profile, each value of the
- 540 CIM_BaseMetricDefinition.BreakdownDimensions property shall be formatted as follows:
- 541 < OrgID > : < LocalID >, where < OrgID > and < LocalID > are separated by a colon (:) and
- 542 < OrgID > shall include a copyrighted, trademarked, or otherwise unique name that is owned by the
- 543 business entity that is creating or defining the value or that is a registered ID assigned to the
- business entity by a recognized global authority. In addition, to ensure uniqueness, < OrgID > shall
- not contain a colon (:). If using this algorithm, the first colon to appear in the value shall appear
- between < OrgID > and < LocalID >. < LocalID > is chosen by the business entity and shall be used
- 547 uniquely.
- If the CIM BaseMetricValue.BreakdownValue identifies a CIM instance, the
- 549 CIM_BaseMetricValue.BreakdownValue property shall be formatted as a WBEM URI (as defined in
- DSP0207) that identifies the CIM instance.
- 551 If the value of the CIM_BaseMetricValue.BreakdownDimension property is not NULL, it shall be one of
- the values contained in the CIM_BaseMetricDefinition.BreakdownDimensions property of the associated
- instance of CIM_BaseMetricDefinition. If the CIM_BaseMetricValue.BreakdownDimension property is
- NULL, the CIM_BaseMetricValue.BreakdownValue property shall be NULL.

555 **7.1.5 Gathering Type**

- 556 If values for an instance of CIM BaseMetricDefinition are gathered through online monitoring, the
- 557 CIM_BaseMetricDefinition.GatheringType property shall have a value of 3 (Periodic) or 2 (OnChange). If
- values for an instance of CIM_BaseMetricDefinition are gathered through snapshot monitoring, the
- 559 CIM_BaseMetricDefinition.GatheringType property shall have a value of 4 (OnRequest).

560 7.2 Modeling Metric Access Types

- This section details requirements for modeling different metric access types. The requirements stated in
- this section for the CIM_BaseMetricDefinition and CIM_BaseMetricValue classes shall also apply to the
- 563 CIM_AggregationMetricDefinition and CIM_AggregationMetricValue subclasses, respectively.

7.2.1 Modeling Current Data Access Type (Optional)

- Metrics with an access type of current data may be supported. If metrics with an access type of current
- data are modeled, the CIM_BaseMetricDefinition and CIM_BaseMetricValue classes shall be used as
- defined in 10.10 and 10.12, respectively.

7.3 Modeling Metric Time Scope

- This section details requirements for modeling metrics with common time scopes. The requirements
- 570 stated in this section for CIM BaseMetricDefinition and CIM BaseMetricValue shall also apply to the
- 571 CIM_AggregationMetricDefinition and CIM_AggregationMetricValue subclasses, respectively.

7.3.1 Modeling Instantaneous Metrics (Optional)

- 573 Instantaneous metrics may be modeled. If instantaneous metrics are modeled, the
- 574 CIM BaseMetricDefinition and CIM BaseMetricValue classes shall be used as defined in 10.6 and 10.11,
- 575 respectively.

568

576

7.3.2 Modeling Interval Metrics (Optional)

- 577 Interval metrics may be modeled. If interval metrics are modeled, the CIM_BaseMetricDefinition and
- 578 CIM BaseMetricValue classes shall be used as defined in 10.7 and 10.13, respectively.

7.3.3 Modeling Interval Metrics (Optional)

- 580 Startup interval metrics may be modeled. If interval metrics are modeled, the CIM_BaseMetricDefinition
- and CIM_BaseMetricValue classes shall be used as defined in 10.8 and 10.14, respectively.

7.4 Modeling Metric Value Formulation

583 This section details requirements for modeling metrics with common value formulations.

7.4.1 Modeling Summation Metrics (Optional)

- 585 Summation metrics may be modeled. If summation metrics are modeled, the CIM_BaseMetricDefinition
- and CIM BaseMetricValue clases shall be used as defined in 10.9 and 10.15, respectively.

7.4.2 Modeling Aggregation Metrics (Optional)

- Aggregation metrics may be modeled. When aggregation metrics are modeled, the requirements
- specified in this section shall be met. An instance of CIM_AggregationMetricDefinition shall define the
- aggregation metric. An instance of CIM_AggregationMetricValue shall exist for each aggregation metric
- 591 value.

592 7.4.2.1 Modeling Low Watermark Metrics (Optional)

- 593 If a low watermark metric is modeled, the instance of CIM_AggregationMetricDefinition that defines the
- metric shall be implemented as defined in 10.2.

595 7.4.2.2 Modeling High Watermark Metrics (Optional)

- 596 If a high watermark metric is modeled, the instance of CIM AggregationMetricDefinition that defines the
- metric shall be implemented as defined in 10.3.

7.5 Relationship between Aggregation and Base Metrics

- If an aggregation metric that is defined by an instance of CIM_AggregationMetricDefinition reports a value
- derived from a base metric that is modeled with an instance of CIM BaseMetricDefinition, the instance of
- 601 CIM_AggregationMetricDefinition may be associated with the instance of CIM_BaseMetricDefinition
- through an instance of CIM_ConcreteDependency, where the instance of CIM_ConcreteDependency is
- as defined in 10.17. If the aggregation metric value modeled with an instance of
- 604 CIM AggregationMetricValue is identical to a base metric value for the base metric definition from which
- the aggregation metric is derived, the instance of CIM AggregationMetricValue may be associated with
- the CIM_BaseMetricValue through an instance of CIM_ConcreteDependency that is implemented as
- 607 defined in 10.18.

608

7.6 Constraints on Metric Values for Controllable Metrics

- The ability to control the collection of a metric defined by an instance of CIM_BaseMetricDefinition for a
- 610 managed element represented by an instance of CIM ManagedElement may be supported.
- 611 If the value of the MetricCollectionEnabled property of the CIM_MetricDefForME instance that associates
- an instance of CIM BaseMetricDefinition with an instance of CIM ManagedElement has the value 3
- 613 (Disabled), an instance of CIM_BaseMetricValue shall not be associated with the
- 614 CIM_BaseMetricDefinition through CIM_MetricInstance where the instance of CIM_BaseMetricValue is
- associated with the CIM_ManagedElement instance through CIM_MetricForME and the value of the
- 616 CIM_BaseMetricValue.Volatile property is 2 (Enabled).

- The value of the RecordedSince property of an instance of CIM_MetricDefForME shall not reflect a value
- earlier in time than the time when the MetricCollectionEnabled property of the instance of
- 619 CIM_MetricDefForME last transitioned from a value of 3 (Disabled) to 2 (Enabled).
- For an instance of CIM_BaseMetricValue that is associated with an instance of CIM_BaseMetricDefinition
- through CIM_MetricInstance and that is associated with an instance of CIM_ManagedElement through
- the CIM_MetricForME association, if an instance of CIM_BaseMetricValue has a value of 2 (Enabled) for
- the Volatile property, the value of the TimeStamp property or the value calculated by subtracting the value
- of the Duration property from the value of the TimeStamp property shall not specify a point in time earlier
- than the value of the RecordedSince property of the instance of CIM_MetricDefForME that associates the
- instance of CIM_BaseMetricDefinition to the instance of CIM_ManagedElement.

8 Methods

627

639

- 628 This section details the requirements for supporting intrinsic operations and extrinsic methods for the CIM
- 629 elements defined by this profile. For the extrinsic methods defined in clauses 8.1 through 8.5, the
- 630 requirements pertaining to the CIM_BaseMetricDefinition and CIM_BaseMetricValue classes shall also
- apply to the CIM AggregationMetricDefinition and CIM AggregationMetricValue subclasses, respectively.

632 8.1 CIM_MetricService.ShowMetrics()

- The ShowMetrics() method provides the ability to query for metrics that a server-side implementation is
- able to collect, as well as whether or not collection of the metric is currently enabled.
- The ShowMetrics() method's return code values shall be as specified in Table 2 where the method
- execution behavior matches the return code description. The ShowMetrics() method's parameters are
- specified in Table 3.
- No standard messages are defined for this method.

Table 2 - CIM MetricService.ShowMetrics() Method: Return Code Values

Value	Description
0	Operation completed successfully
1	Operation unsupported
2	Failed

640

641

648

655

Table 3 – CIM_MetricService.ShowMetrics() Method: Parameters

Qualifiers	Name	Туре	Description/Values
IN	Subject	CIM_ManagedElement REF	Reference to the CIM_ManagedElement for which metrics will be reported
IN	Definition	CIM_BaseMetricDefinition REF	Reference to the CIM_BaseMetricDefinition to query for values of
OUT	ManagedElements	CIM_ManagedElement REF[]	Array of references to instances of CIM_ManagedElement for which the metric identified by the Definition parameter is being collected
OUT	DefinitionList	REF[]	Array of references to instances of CIM_BaseMetricDefinition defining metrics being collected for the CIM_ManagedElement instance identified by the Subject parameter
OUT	MetricNames	string[]	Array of metric names for the instances of CIM_BaseMetricDefinition specified by the DefinitionList parameter
OUT	MetricCollectionEnabled	uint16[]	Array of values indicating whether or not a metric is being collected

8.1.1 CIM_MetricService.ShowMetrics() Conditional Support

- If the SupportedMethods property array of the associated instance of CIM_MetricServiceCapabilities contains the value 4 (ShowMetrics), the ShowMetrics() method shall be implemented and shall not return the value 1 (Not Supported).
- If the SupportedMethods property array of the associated instance of CIM_MetricServiceCapabilities does not contain the value 4 (ShowMetrics), the ShowMetrics() method shall not be implemented or shall always return the value 1 (Not Supported).

8.2 CIM_MetricService.ShowMetricsByClass()

- The ShowMetricsByClass() method provides the ability to query for metrics that a server-side implementation is able to collect, as well as whether or not collection of the metric is currently enabled.
- The ShowMetricsByClass() method's return code values shall be as specified in Table 4 where the method execution behavior matches the return code description. The ShowMetricsByClass() method's parameters are specified in Table 5.
- No standard messages are defined for this method.

Table 4 - CIM_MetricService.ShowMetricsByClass() Method: Return Code Values

Value	Description	
0 Operation completed successfully		
1	Operation unsupported	
2	Failed	

Table 5 – CIM_MetricService.ShowMetricsByClass() Method: Parameters

Qualifiers	Name	Туре	Description/Values
IN	Subject	CIM_ManagedElement REF	Identifies a CIM class for which metrics will be reported
IN	Definition	CIM_BaseMetricDefinition REF	Reference to the CIM_BaseMetricDefinition to query for values of
OUT	DefinitionList	REF[]	Array of references to instances of CIM_BaseMetricDefinition defining metrics being collected for the CIM class identified by the Subject parameter
OUT	MetricNames	string[]	Array of metric names for the instances of CIM_BaseMetricDefinition specified by the DefinitionList parameter
OUT	MetricCollectionEnabled	uint16[]	Array of values indicating whether or not a metric is being collected

657 8.2.1 CIM_MetricService.ShowMetricsByClass() Conditional Support

If the SupportedMethods property array of the associated instance of CIM_MetricServiceCapabilities contains the value 5 (ShowMetricsByClass), the ShowMetricsByClass() method shall be implemented and shall not return the value 1 (Not Supported).

If the SupportedMethods property array of the associated instance of CIM_MetricServiceCapabilities does not contain the value 5 (ShowMetricsByClass), the ShowMetricsByClass() method shall not be implemented or shall always return the value 1 (Not Supported).

8.3 CIM_MetricService.ControlMetrics()

656

661

662

663

664

665

666 667

668 669

670

671

672

673

The ControlMetrics() method provides the ability to enable or disable the collection of:

- a metric for all instances of CIM_ManagedElement
- all metrics for a single CIM_ManagedElement instance
- a single metric for a single CIM_ManagedElement instance

The ControlMetrics() method's return code values shall be as specified in Table 6 where the method execution behavior matches the return code description. The ControlMetrics() method's parameters are specified in Table 7.

No standard messages are defined for this method.

Table 6 - CIM_MetricService.ControlMetrics() Method: Return Code Values

Value	Description	
0	Operation completed successfully	
1	Operation unsupported	
2	Failed	

674 Table 7 – CIM_MetricService.ControlMetrics() Method: Parameters

Qualifiers	Name	Туре	Description/Values
IN	Subject	CIM_ManagedElement REF	Reference to the CIM_ManagedElement for which metrics will be controlled
IN	Definition	CIM_BaseMetricDefinition REF	Reference to the CIM_BaseMetricDefinition for which collection is to be enabled or disabled
IN, REQ	MetricCollectionEnabled	uint16	Value indicating whether or not the metric is collected

8.3.1 CIM_MetricService.ControlMetrics() Conditional Support

If the SupportedMethods property array of the associated instance of CIM_MetricServiceCapabilities contains the value 2 (ControlMetrics), the ControlMetrics() method shall be implemented and shall not return the value 1 (Not Supported).

If the SupportedMethods property array of the associated instance of CIM_MetricServiceCapabilities does not contain the value 2 (ControlMetrics), the ControlMetrics() method shall not be implemented or shall always return the value 1 (Not Supported).

8.3.2 Parameter Validation

If the Subject parameter is NULL and the instance of CIM_BaseMetricDefinition that is identified by the
Definition parameter is not identified by a value of the ControllableMetrics property of the associated
instance of CIM_MetricServiceCapabilities where the corresponding array index of the
MetricsControlTypes property of the CIM_MetricServiceCapabilities instance has the value 3 (Bulk) or 4
(Both), the method shall return a value of 2 (Failed).

If the Definition parameter is NULL and the instance of CIM_ManagedElement identified by the Subject parameter is not identified by a value of the ControllableManagedElement property of the associated instance of CIM_MetricServiceCapabilities where the corresponding array index of the ManagedElementControlTypes property of the CIM_MetricServiceCapabilities instance has the value 3 (Bulk) or 4 (Both), the method shall return a value of 2 (Failed).

If both the Subject and Definition parameters are non-null, the method shall return a value of 2 (Failed) if neither of the following conditions is met:

- The instance of CIM_ManagedElement identified by the Subject parameter is identified by a value of the ControllableManagedElements property of the associated instance of CIM_MetricServiceCapabilities, where the corresponding array index of the ManagedElementControlTypes property of the CIM_MetricServiceCapabilities instance has a value of 2 (Discrete), and the instance of CIM_BaseMetricDefinition identified by the Definition parameter is identified by a value of the ControllableMetrics property of the associated instance of CIM_MetricServiceCapabilities, where the corresponding array index of the MetricsControlTypes property of the CIM_MetricServiceCapabilities instance has a value of 2 (Discrete).
- The instance of CIM_BaseMetricDefinition identified by the Definition parameter is identified by a value of the ControllableMetrics property of the associated instance of CIM_MetricServiceCapabilities, where the corresponding array index of the MetricsControlTypes property of the CIM_MetricServiceCapabilities instance has a value of 2 (Discrete) and no instances of CIM_ManagedElement that are associated with the CIM_BaseMetricDefinition through the CIM_MetricDefForME are identified by a value of the ControllableManagedElements property of the associated instance of CIM_MetricServiceCapabilities.

NOTE: The effect of the second condition is to allow the advertisement of support for controlling the collection of every metric value for a CIM_BaseMetricDefinition instance without having to explicitly list each CIM_ManagedElement instance in the ControllableManagedElements property.

8.4 CIM_MetricService.ControlMetricsByClass()

- The ControlMetricsByClass() method provides the ability to enable or disable the collection of:
- a metric for all instances of a specific CIM class
- 718 all metrics for all instances of a specific CIM class
- 719 a single metric for a single CIM ManagedElement
- The ControlMetricsByClass() method's return code values shall be as specified in Table 8 where the
- method execution behavior matches the return code description. The ControlMetricsByClass() method's
- 722 parameters are specified in Table 9.

715

724

725

726

733

No standard messages are defined for this method.

Table 8 – CIM_MetricService.ControlMetricsByClass() Method: Return Code Values

Value	Description	
0	Operation completed successfully	
1	Operation unsupported	
2	Failed	

Table 9 – CIM_MetricService.ControlMetricsByClass() Method: Parameters

Qualifiers	Name	Туре	Description/Values
IN	Subject	CIM_ManagedElement REF	Reference to the CIM class for which metrics will be controlled
IN	Definition	CIM_BaseMetricDefinition REF	Reference to the CIM_BaseMetricDefinition for which collection is to be enabled or disabled
IN, REQ	MetricCollectionEnabled	uint16	Value indicating whether the metric is to be enabled or disabled

8.4.1 CIM MetricService.ControlMetricsByClass() Conditional Support

- 727 If the SupportedMethods property array of the associated instance of CIM_MetricServiceCapabilities
- 728 contains the value 3 (ControlMetricsByClass), the ControlMetricsByClass() method shall be implemented
- and shall not return the value 1 (Not Supported).
- 730 If the SupportedMethods property array of the associated instance of CIM_MetricServiceCapabilities does
- 731 not contain the value 3 (ControlMetricsByClass), the ControlMetricsByClass() method shall not be
- implemented or shall always return the value 1 (Not Supported).

8.4.2 Parameter Validation

- 734 If the Subject parameter is NULL and the instance of CIM BaseMetricDefinition that is identified by the
- 735 Definition parameter is not identified by a value of the ControllableMetrics property of the associated
- 736 instance of CIM MetricServiceCapabilities where the corresponding array index of the
- 737 MetricsControlTypes property of the CIM MetricServiceCapabilities instance has the value 3 (Bulk) or 4
- 738 (Both), the method shall return a value of 2 (Failed).

739 8.5 CIM_MetricService.GetMetricValues()

- 740 The GetMetricValues() method provides the ability to query for metric values.
- The GetMetricValues() method's return code values shall be as specified in Table 10 where the method
- execution behavior matches the return code description. The GetMetricValues() method's parameters are
- 743 specified in Table 11.

745

746

754

No standard messages are defined for this method.

Table 10 – CIM_MetricService.GetMetricValues() Method: Return Code Values

Value	Description	
0	Operation completed successfully	
1	Operation unsupported	
2	Failed	

Table 11 - CIM MetricService.GetMetricValues() Method: Parameters

Qualifiers	Name	Туре	Description/Values
IN	Definition	CIM_BaseMetricDefinition REF	Reference to the CIM_BaseMetricDefinition to query for values
IN	Range	uint16	Identifies how the values are selected
IN	Count	uint16	Identifies the maximum number of instances to return
OUT	Values	CIM_BaseMetricValue REF[]	Array of references to instances of CIM_BaseMetricValue corresponding to the CIM_BaseMetricValue instances that match the query constraints identified by the input parameters

747 8.5.1 CIM_MetricService.GetMetricValues() Conditional Support

- 748 If the SupportedMethods property array of the associated instance of CIM_MetricServiceCapabilities
- 749 contains the value 6 (GetMetricValues), the GetMetricValues() method shall be implemented and shall
- not return the value 1 (Not Supported).
- 751 If the SupportedMethods property array of the associated instance of CIM_MetricServiceCapabilities does
- 752 not contain the value 6 (GetMetricValues), the GetMetricValues() method shall not be implemented or
- shall always return the value 1 (Not Supported).

8.6 Profile Conventions for Operations

- For each profile class (including associations), the implementation requirements for operations, including those in the following default list, are specified in class-specific subclauses of this clause.
- 757 The default list of operations is as follows:
- GetInstance
- 759 Associators
- AssociatorNames
- 761 References

- 762 ReferenceNames
- EnumerateInstances
- EnumerateInstanceNames

765 8.7 CIM_AggregationMetricDefinition

- 766 All operations in the default list in 8.6 shall be implemented as defined in DSP0200.
- 767 NOTE: Related profiles may define additional requirements on operations for the profile class.

768 8.8 CIM_AggregationMetricValue

- 769 All operations in the default list in 8.6 shall be implemented as defined in <u>DSP0200</u>.
- 770 NOTE: Related profiles may define additional requirements on operations for the profile class.

771 8.9 CIM BaseMetricDefinition

- 772 All operations in the default list in 8.6 shall be implemented as defined in DSP0200.
- 773 NOTE: Related profiles may define additional requirements on operations for the profile class.

774 8.10 CIM BaseMetricValue

- All operations in the default list in 8.6 shall be implemented as defined in <u>DSP0200</u>.
- 776 NOTE: Related profiles may define additional requirements on operations for the profile class.

777 8.11 CIM_ConcreteDependency

- 778 Table 12 lists implementation requirements for operations. If implemented, these operations shall be
- implemented as defined in <u>DSP0200</u>. In addition, and unless otherwise stated in Table 12, all operations
- in the default list in 8.6 shall be implemented as defined in DSP0200.
- 781 NOTE: Related profiles may define additional requirements on operations for the profile class.

782 Table 12 – Operations: CIM ConcreteDependency

Operation	Requirement	Messages
Associators	Unspecified	None
AssociatorNames	Unspecified	None
References	Unspecified	None
ReferenceNames	Unspecified	None
EnumerateInstances	Unspecified	None
EnumerateInstanceNames	Unspecified	None

783 8.12 CIM_ElementCapabilities

- Table 13 lists implementation requirements for operations. If implemented, these operations shall be implemented as defined in <u>DSP0200</u>. In addition, and unless otherwise stated in Table 13, all operations in the default list in 8.6 shall be implemented as defined in <u>DSP0200</u>.
- 787 NOTE: Related profiles may define additional requirements on operations for the profile class.

788

Table 13 – Operations: CIM_ElementCapabilities

Operation	Requirement	Messages
Associators	Unspecified	None
AssociatorNames	Unspecified	None
References	Unspecified	None
ReferenceNames	Unspecified	None
EnumerateInstances	Unspecified	None
EnumerateInstanceNames	Unspecified	None

789 8.13 CIM_HostedService

Table 14 lists implementation requirements for operations. If implemented, these operations shall be implemented as defined in <u>DSP0200</u>. In addition, and unless otherwise stated in Table 14, all operations in the default list in 8.6 shall be implemented as defined in <u>DSP0200</u>.

NOTE: Related profiles may define additional requirements on operations for the profile class.

794

795

796

797

798

793

Table 14 - Operations: CIM_HostedService

Operation	Requirement	Messages
Associators	Unspecified	None
AssociatorNames	Unspecified	None
References	Unspecified	None
ReferenceNames	Unspecified	None
EnumerateInstances	Unspecified	None
EnumerateInstanceNames	Unspecified	None

8.14 CIM_MetricDefForME

Table 15 lists implementation requirements for operations. If implemented, these operations shall be implemented as defined in <u>DSP0200</u>. In addition, and unless otherwise stated in Table 15, all operations in the default list in 8.6 shall be implemented as defined in <u>DSP0200</u>.

NOTE: Related profiles may define additional requirements on operations for the profile class.

800 Table 15 – Operations: CIM_MetricDefForME

Operation	Requirement	Messages
Associators	Unspecified	None
AssociatorNames	Unspecified	None
References	Unspecified	None
ReferenceNames	Unspecified	None
EnumerateInstances	Unspecified	None
EnumerateInstanceNames	Unspecified	None

8.15 CIM MetricForME

801

805

807

808

809 810

811

813

815

Table 16 lists implementation requirements for operations. If implemented, these operations shall be implemented as defined in <u>DSP0200</u>. In addition, and unless otherwise stated in Table 16, all operations in the default list in 8.6 shall be implemented as defined in <u>DSP0200</u>.

NOTE: Related profiles may define additional requirements on operations for the profile class.

806 Table 16 – Operations: CIM_MetricForME

Operation	Requirement	Messages
Associators	Unspecified	None
AssociatorNames	Unspecified	None
References	Unspecified	None
ReferenceNames	Unspecified	None
EnumerateInstances	Unspecified	None
EnumerateInstanceNames	Unspecified	None

8.16 CIM_MetricInstance

Table 17 lists implementation requirements for operations. If implemented, these operations shall be implemented as defined in <u>DSP0200</u>. In addition, and unless otherwise stated in Table 17, all operations in the default list in 8.6 shall be implemented as defined in <u>DSP0200</u>.

NOTE: Related profiles may define additional requirements on operations for the profile class.

812 Table 17 – Operations: CIM_MetricInstance

Operation	Requirement	Messages
Associators	Unspecified	None
AssociatorNames	Unspecified	None
References	Unspecified	None
ReferenceNames	Unspecified	None
EnumerateInstances	Unspecified	None
EnumerateInstanceNames	Unspecified	None

8.17 CIM MetricService

All operations in the default list in 8.6 shall be implemented as defined in DSP0200.

8.18 CIM_MetricServiceCapabilities

All operations in the default list in 8.6 shall be implemented as defined in DSP0200.

8.19 CIM ServiceAffectsElement

817

822

825

829

Table 18 lists implementation requirements for operations. If implemented, these operations shall be

implemented as defined in <u>DSP0200</u>. In addition, and unless otherwise stated in Table 18, all operations

- in the default list in 8.6 shall be implemented as defined in <u>DSP0200</u>.
- 821 NOTE: Related profiles may define additional requirements on operations for the profile class.

Table 18 – Operations: CIM_ServiceAffectsElement

Operation	Requirement	Messages
Associators	Unspecified	None
AssociatorNames	Unspecified	None
References	Unspecified	None
ReferenceNames	Unspecified	None
EnumerateInstances	Unspecified	None
EnumerateInstanceNames	Unspecified	None

9 Use Cases (Informative)

824 This section contains object diagrams and use cases for the Base Metrics Profile.

9.1 Instructions Executed per Second

- 826 This section contains object diagrams showing several implementations of metrics related to the
- 827 execution of processor instructions. A management client can use each different type of metric provided
- 828 to determine the instructions executed per second (IEPS) for the operating system.

9.1.1 Interval Metrics

- Figure 2 presents an object diagram for an implementation of an interval metric showing the instructions
- 831 executed per second for an operating system image. There is one instance of the BaseMetricValue class
- with a TimeStamp property value of 07:25:00 A.M. at 9/4/2006, a Duration property value of 60 seconds
- and a metric value of 100 million, meaning that the instrumented server has executed 100 million
- instructions on 9/4/2006 between 07:24:00 A.M. and 07:25:00 A.M. The measured element in this
- example is an instance of CIM_OperatingSystem. A management client could calculate the average
- instructions executed per second from 07:24:00 A.M. to 07:25:00 A.M. by dividing the total number of
- instructions (100 million) by the duration (60 seconds).
- 838 The CIM_BaseMetricDefinition.Id property contains a UUID that is chosen by the metrics provider.
- The DataType is set to 13 (uint64), which means that the metric values associated to this metric definition
- instance are intended to be of type uint64.
- TimeScope 3 (Interval) means that the metric values are related to a time interval. The values of the
- TimeStamp and Duration properties indicate that the monitored interval is 09/04/2006 7:24 A.M. UTC
- through 09/04/2006 7:25 A.M. UTC. The MetricValue property indicates that the operating system has
- executed 100 million instructions between 7:24:00 A.M. UTC and 7:25:00 A.M. UTC.
- 845 GatheringType 3 (Periodic) means that the underlying gathering infrastructure is capturing new counters
- 846 periodically. How frequently the metric is captured is not indicated. An example would be once a minute.





Figure 2 – Interval Metrics 849

9.1.2 Instantaneous Counter

The object diagram in Figure 3 shows a possible implementation of an instantaneous metric reporting the number of instructions executed. There is exactly one instance of class CIM_BaseMetricValue. The client has executed a GetInstance operation at one minute intervals to query the current values of the metric. The object diagram shows the last retrieved instance using the standard notation. The box with the rounded corners shows the same instance retrieved one minute earlier. A management client can calculate the average IEPS by calculating the delta between the MetricValue properties for the two instances and dividing it by the delta between the TimeStamp properties of the two instances.



860 Figure 3 – Instantaneous Counter

9.1.3 Instantaneous Gauge

Figure 4 shows an object diagram in which average instructions per second are directly instrumented. The underlying system provides a metric that corresponds to the average number of instructions per second. However, it does not provide information about the duration over which the average was calculated. This is sometimes known as an instantaneous average.

The ProgrammaticUnits property indicates that the metric reports millions of instructions per second. The CIM BaseMetricDefinition.TimeScope property indicates that the metric is an interval metric. The CIM BaseMetricValue.Duration property indicates that there is no precision to the reported interval duration. The current values of the properties of the CIM_BaseMetricValue instance indicate that, as of 07:25:00 A.M. at 9/4/2006, an average of 100 million instructions were executed per second.

871

873

861

862

863

864

865

866

867

868

869




Figure 4 – Instantaneous Gauge

9.2 Object Diagram for Startup Interval Time Scope

A value of 4 (StartupInterval) for the TimeScope property indicates that the metric applies to an interval that began at the startup of the measured resource. The example in Figure 5 shows that at 07:25:00 A.M. on 09/04/2006, the associated application system "DB2 V9.1 on tux4ever" was running for a duration of 977 days and 5 hours, consuming 100 million resources. The associated metric is "InstructionsExecuted", with a unit of "Million Count" of instructions.




Figure 5 – Usage Example for Startup Interval Time Scope

Version 1.0.1 DMTF Standard 33

9.3 Metric Definition for Multiple Instances of CIM_ManagedElement

Figure 6 is an object diagram for an implementation that reports the same metric for two managed elements. metval1 and metval2 report the standard metric "xyz:InstructionsPerSecond" for cpu1 and cpu2, respectively.

886

888

882

883




Figure 6 - Common Metric Definition for Multiple Instances of CIM ManagedElement

9.4 Controllable Metrics

Figure 7 shows an object diagram for an implementation in which a single metric, represented by the CIM_BaseMetricDefinition instance bmd1, is available for two processors, represented by CIM_Processor instances cpu1 and cpu2. Enabling and disabling the collection of the metric for cpu1 and cpu2 is performed separately. The capabilities for controlling metric collection are indicated by capabilities1. The value of the ControllableMetrics property is bmd1, which indicates that some amount of control over metric collection for values of bmd1 is supported. The value of the MetricControlTypes property is 2 (Discrete), which indicates that metric collection can be controlled for individual values. The value of the ControllableManagedElements property is NULL or empty. The absence of a specific list of CIM_ManagedElement instances associated with bmd1 indicates that controlling metric collection for all metric values of bmd1 is supported. The CIM_ServiceAffectsElement associations between the CIM_MetricService instance and the CIM_BaseMetricDefinition instances have been elided.




Figure 7 – Advertising Support for Discrete Controllable Metrics

Figure 8 shows an object diagram for an implementation in which a single metric, represented with the CIM_BaseMetricDefinition instance bmd1, is available for two processors, represented by the CIM_Processor instances cpu1 and cpu2.

The ability to control metrics supported by the implementation shown in Figure 8 is identical to those of the implementation shown in Figure 7. Figure 8 shows an alternate method of advertising the support. The value of the ControllableMetrics property is bmd1, which indicates that some amount of control over metric collection for values of bmd1 is supported. The value of the MetricControlTypes property is 2 (Discrete), which indicates that metric collection can be controlled for individual values. The value of the ControllableManagedElements property is cpu1 and cpu2, which indicates that some amount of control over metrics for cpu1 and cpu2 is supported.

In the object diagram shown in Figure 8, collection of the metric for cpu1 has been disabled. This is indicated by the value of the MetricCollectionEnabled property of the instance of CIM_MetricDefForME that associates bmd1 with cpu1. The CIM_ServiceAffectsElement associations between the CIM MetricService instance and the CIM BaseMetricDefinition instances have been elided.




Figure 9 shows an object diagram for the system shown in Figure 8. The CIM_MetricService.ControlMetrics() method has been used to enable the collection of the metric represented by the bmd1 instance for cpu1. The CIM_ServiceAffectsElement associations between the CIM_MetricService instance and the CIM_BaseMetricDefinition instances have been elided.

920

921

922

923

924

925




Figure 9 – Discrete Controllable Metrics (After Enable)

Version 1.0.1 DMTF Standard 37

Figure 10 shows an object diagram for an implementation where two metrics, represented by the CIM_BaseMetricDefinition instances bmd1 and bmd2, are available for two processors, represented by CIM_Processor instances cpu1 and cpu2. The collection of all metric values for the bmd2 instance is controlled as a single operation. The collection of metric values for the bmd1 instance is controlled discretely for each metric value. In the object diagram shown in Figure 10, collection of the metric represented by bmd2 has been disabled. This is indicated by the value of the MetricCollectionEnabled property of the instances of CIM_MetricDefForME that associate bmd2 with cpu1 and cpu2. The CIM_ServiceAffectsElement associations between the CIM_MetricService instance and the CIM_BaseMetricDefinition instances have been elided.




Figure 10 - Bulk Controllable Metrics by Definition

Figure 11 shows an object diagram for an implementation in which two metrics, represented by the CIM BaseMetricDefinition instances bmd1 and bmd2, are available for three processors, represented by CIM Processor instances cpu1, cpu2, and cpu3. The collection of all metric values for bmd2 is controlled as a single operation. The collection of metric values for bmd1 is controlled discretely for each metric value. In the object diagram shown in Figure 11, collection of metric values for bmd2 has been disabled. This is indicated by the value of the MetricCollectionEnabled property of the instances of CIM_MetricDefForME that associate bmd2 with cpu3 and cpu2. The CIM_ServiceAffectsElement associations between the CIM MetricService instance and the CIM BaseMetricDefinition instances have been elided.




Figure 11 – Bulk Controllable Metrics by Managed Element

Version 1.0.1 **DMTF Standard** 39

947

948

938

939

940


941

942

943

944

Figure 12 shows an object diagram for an implementation in which a single metric is available for three processors, represented by instances of subclasses of CIM_Processor cpu1, cpu2, and cpu3. Two instances of CIM_BaseMetricDefinition (bmd1 and bmd2) define the same standard metric "xyz:InstructionsPerSection". Multiple instances of the CIM_BaseMetricDefinition class are required in order to represent the separate control points for collection of the metric values. The collection of bmd2 is controlled for all instances of the yyy_Processor class as a bulk operation. Control of the collection of the metric value defined by bmd1 for cpu1 is not supported. The CIM_ServiceAffectsElement associations between the CIM_MetricService instance and the CIM_BaseMetricDefinition instances have been elided.



959 Figure 12 – Bulk Controllable Metrics by Class

9.5 Aggregation Metrics

960

961

962

963

964

965

Figure 13 shows an object diagram for an implementation that supports reporting a high watermark for the number of instructions per second executed on a processor. The maximum value in the approximate interval from 12/28/2005 through 11/04/2006 occurred on 09/04/2006 at 7:25 A.M. UTC.




Figure 13 – Aggregation Metric without Base

Version 1.0.1 DMTF Standard 41

Figure 14 shows an object diagram for an implementation that provides the same function as the implementation shown in Figure 13 with the additional functionality of supporting the underlying base metric. The information that bmd1 is the base metric for amd1 is conveyed by the instance of CIM_ConcreteDependency that associates them. In this implementation, long-term monitoring is supported for bmd1; hence, the instance metval1 exists even though it represents historical data.




Figure 14 - Aggregation Metric with Base

971

972

42 DMTF Standard Version 1.0.1

9.6 Metric Context

Figure 15 illustrates the use of breakdown dimensions to differentiate among multiple instances of CIM_BaseMetricValue that provide instances of the same metric definition. metval1 and metval2 are instances of the metric that indicate the instructions per second consumed by process1 from cpu1 and cpu2, respectively. metval3 provides information about the total instructions per second utilized by process1 from all processors.




Figure 15 – Metric Context

9.7 Find All Metric Definitions for a Managed Element

982

984 985

986

987

988

989

990

991 992

993

994

995

996

997

998 999

1000 1001

1002

1003

1004

1005

1006

1007

1008

1009

1010

1011

1013

983 A client can find all of the metric definitions available for a Managed Element as follows:

1) Starting at the instance of CIM_ManagedElement, find all instances of CIM_BaseMetricDefinition associated with the CIM_ManagedElement instance through the CIM_MetricDefForME association.

9.8 Find the Metric Value for a Managed Element

Given an instance of CIM_BaseMetricDefinition that is associated with the CIM_ManagedElement instance through a CIM_MetricDefForME association, a client can find the metric value for the CIM_ManagedElement as follows:

- 1) Find the instance of CIM_MetricDefForME that associates the CIM_BaseMetricDefinition with the CIM_ManagedElement instance.
- 2) If the value of the MetricCollectionEnabled property of the instance of CIM_MetricDefForME association found in the previous step is 2 (Enabled):
 - a) Find all instances of CIM_BaseMetricValue associated with the CIM_BaseMetricDefinition through the CIM_MetricInstance association.
 - b) Find all instances of CIM_BaseMetricValue associated with the CIM_ManagedElement instance through CIM_MetricForME.
 - c) Find the instance of CIM_BaseMetricValue that is the intersection of the two result sets by finding matching InstanceID property values.
- 3) Otherwise, metric collection is disabled and a current data metric value is not available.

9.9 Find a Standard Metric for a Managed Element

Given a string value corresponding to the unique identifier of a standard metric, a client can find the standard metric value for an instance of CIM ManagedElement as follows:

- 1) Use the steps in 9.6 to find all metric definitions available for the instance of CIM_ManagedElement.
- 2) For each instance of CIM_BaseMetricDefinition returned, determine if the Name property matches the string identifier. If there is a match, use the steps in 9.8 to find the metric value.
- 3) If a matching Name property is not found, the standard metric is not supported for the instance of CIM ManagedElement.

9.10 Retrieve a Metric Value

- 1012 A client can retrieve a metric value as follows:
 - 1) Using the steps in 9.9, find the instance of CIM BaseMetricValue that reports the metric.
- 1014 2) Invoke GetInstance to query the current values of properties of the CIM_BaseMetricValue instance.

9.11 Find All Metrics Available for a Managed Element within an Enumeration Scope

Given an instance of CIM_ManagedElement, a client can find all of the metrics available for an instance of CIM_ManagedElement as follows:

- 1) Enumerate all instances of CIM_MetricService within the enumeration scope.
 - a) For each instance of CIM_MetricService, find the instance of CIM_MetricServiceCapabilities associated through CIM_ElementCapabilities.
 - b) Query the value of the CIM_MetricServiceCapabilities.SupportedMetrics property.
 - If the array contains the value 4 (Show Metrics), invoke the CIM_MetricService.ShowMetrics() method providing the reference to the CIM_ManagedElement.
 - d) The list of references to CIM_BaseMetricDefinition returned as the value of the Definitions parameter identifies instances of CIM_BaseMetricDefinition that are available for the CIM_ManagedElement instance.
- 2) Starting with a reference to the instance of CIM_ManagedElement, find all instances of CIM_MetricDefinition that are associated through CIM_MetricDefForME.
- 3) Union the results of d) and 2).

1016

1017

1020

1021

1022

1023

1024 1025

1026

1027

1028 1029

1030

1031

1032 1033

1034

1035

1036

1037

10381039

1040

1041

10421043

1044 1045

1046 1047

1048 1049

1050

9.12 Find All Metrics Available within an Enumeration Scope for All Instances of a CIM Class

Given a CIM class name, a client can find all of the metrics available within an enumeration scope for all instances of the class as follows:

- 1) Enumerate all instances of CIM MetricService within the enumeration scope.
 - a) For each instance of CIM_MetricService, find the instance of CIM_MetricServiceCapabilities associated through CIM_ElementCapabilities.
 - b) Query the value of the CIM MetricServiceCapabilities.SupportedMetrics property.
 - c) If the array contains the value 5 (ShowMetricsByClass), invoke the CIM_MetricService.ShowMetrics() method providing the reference to the CIM_ManagedElement.
 - d) The list of references to CIM_BaseMetricDefinition returned as the value of the Definitions parameter identifies instances of CIM_BaseMetricDefinition that are available for the CIM_ManagedElement instance.
- Enumerate all instances of the CIM class.
 - a) For each instance of the CIM class, find all instances of CIM_BaseMetricDefinition that are associated through CIM_MetricDefForME.
 - 3) Form a set of instances of CIM_BaseMetricDefinition from the intersection of the instances returned by a).
- 1051 4) Union the results of d) and 3).

9.13 Determine whether a Metric Can Be Discretely Controlled for a Specific Managed Element

1052

1053

1054

1055

1056

1057

10581059

1060 1061

1062

1063

1064 1065

1066 1067

1068 1069

10701071

1072

1076

1077

1078

1079 1080

1081

1082

1083

1084

1085 1086

1087

1088

1089

1090 1091

1092

1093

1094

Given an instance of CIM_BaseMetricDefinition associated to an instance of CIM_ManagedElement through CIM_MetricDefForME, a client can determine whether the metric can be controlled for the managed element as follows:

- 1) Starting with the instance of CIM_BaseMetricDefinition, find the instance of CIM_MetricService associated through CIM_ServiceAffectsElement.
- 2) Find the instance of CIM_MetricServiceCapabilities associated through CIM_ElementCapabilities with the instance of CIM_MetricService found in 1).
- 3) If the following conditions are met, the metric can be discretely controlled for the managed element:
 - a) The CIM_MetricServiceCapabilities.ControllableMetrics property contains a reference to the CIM_BaseMetricDefinition.
 - b) The CIM_MetricServiceCapabilities.MetricControlTypes property contains the value 2 (Discrete) or 4 (Both) at the same array index as the reference in the previous step.
 - c) The CIM_MetricServiceCapabilities.ControllableManagedElements property contains a reference to the CIM_ManagedElement.
 - d) The CIM_MetricServiceCapabilities.ManagedElementControlTypes property contains the value 2 (Discrete) or 4 (Both) at the same array index as the reference in the previous step.
- 4) Otherwise, the metric can not be discretely controlled for the managed element.

9.14 Enable a Specific Metric for a Specific Managed Element

- Given an instance of CIM_BaseMetricDefinition that is associated to an instance of CIM_ManagedElement through the CIM_MetricDefForME association, a client can enable a specific metric for the managed element as follows:
 - 1) Use the steps in 9.13 to determine whether the metric can be controlled.
 - 2) Invoke the CIM_MetricService.ControlMetrics() method and specify the reference to the CIM_ManagedElement as the value of the Subject parameter, the reference to the CIM_BaseMetricDefinition as the value of the Definition parameter, and TRUE as the value of the MetricCollectionEnabled parameter.

9.15 Find All Managed Elements within an Enumeration Scope for which a Metric Is Currently Being Collected

Given an instance of CIM_BaseMetricDefinition, a client can find all instances of CIM_ManagedElement for which the metric is available as follows:

- 1) Find the instance of CIM_MetricService associated with the CIM_BaseMetricDefinition through the CIM_ServiceAffectsElement association.
- 2) Find the instance of CIM_MetricServiceCapabilities associated with the CIM_MetricService found in the previous step.
- 3) Query the value of the SupportedMethods property of the instance of CIM_MetricServiceCapabilities found in the previous step to determine if it contains a value of 4 (ShowMetrics):
 - a) If the SupportedMethods property contains a value of 4 (ShowMetrics):
 - Invoke the CIM_MetricService.ShowMetrics() method, specifying the reference to the CIM_BaseMetricDefinition as the value of the Definition parameter.

the metric may be collected and the MetricCollectionEnabled property indicates whether the

1095 Upon successful completion of the method, the ManagedElements parameter contains a list of references to CIM ManagedElement instances for which the metric 1096 defined by the CIM BaseMetricDefinition is available. The MetricCollectionEnabled 1097 1098 property indicates whether the metric is currently being collected for the 1099 CIM ManagedElement instance. 1100 If the SupportedMethods property does not contain the value 4, find all instances of CIM_MetricDefForME that reference the CIM_BaseMetricDefinition instance. For each instance 1101 1102 of CIM_MetricDefForME, the Antecedent property identifies a CIM_ManagedElement for which

10 CIM Elements

metric is currently being collected.

1103 1104

1105

1106

1107

1108

1109

1110

Table 19 shows the instances of CIM Elements for this profile. Instances of the CIM Elements shall be implemented as described in Table 19. Sections 7 ("Implementation") and 8 ("Methods") may impose additional requirements on these elements.

Table 19 - CIM Elements: Base Metrics Profile

Element Name	Requirement	Description
Classes		
CIM_AggregationMetricDefinition	Optional	See 10.1, 10.2, and 10.3.
CIM_AggregationMetricValue	Optional	See 10.4.
CIM_BaseMetricDefinition	Optional	See 10.5, 10.6, 10.7, 10.8, 10.9, and 10.10.
CIM_BaseMetricValue	Optional	See 10.11, 10.12, 10.13, 10.15, and 10.16.
CIM_ConcreteDependency	Optional	See 10.17 and 10.18.
CIM_ElementCapabilities	Mandatory	See 10.19.
CIM_HostedService	Mandatory	See 10.20.
CIM_MetricDefForME	Mandatory	See 10.21.
CIM_MetricForME	Conditional	See 10.22.
CIM_MetricInstance	Conditional	See 10.23.
CIM_MetricService	Mandatory	See 10.24.
CIM_MetricServiceCapabilities	Mandatory	See 10.25.
CIM_RegisteredProfile	Mandatory	See 10.26.
CIM_ServiceAffectsElement	Mandatory	See 10.27.
Indications		
None defined in this profile		

10.1 CIM_AggregationMetricDefinition

1111 CIM_AggregationMetricDefinition defines a metric that can be captured. Table 20 defines the 1112 requirements for instances of CIM_AggregationMetricDefinition. This class is used as a basis for 10.2 and 1113 for 10.3.

Version 1.0.1 DMTF Standard 47

1114

1118

1122

Table 20 - Class: CIM_AggregationMetricDefinition

Properties	Requirement	Notes
BreakdownDimensions	Optional	None
Calculatable	Optional	None
ChangeType	Mandatory	Matches 5 (Simple Function)
DataType	Mandatory	None
ElementName	Mandatory	Pattern (".+")
GatheringType	Mandatory	None
ld	Mandatory	Key
IsContinuous	Optional	None
TimeScope	Optional	None
ProgrammaticUnits	Mandatory	None
Name	Mandatory	See 7.1.3.
SimpleFunction	Mandatory	None

1115 10.2 CIM_AggregationMetricDefinition (Low Watermark)

Table 21 defines the requirements for instances of CIM_AggregationMetricDefinition used to define a low watermark metric. These constraints are in addition to those specified in 10.1.

Table 21 – Class: CIM_AggregationMetricDefinition (Low Watermark)

Properties	Requirement	Notes
SimpleFunction	Mandatory	Matches 2 (Minimum)

1119 **10.3 CIM_AggregationMetricDefinition (High Watermark)**

Table 22 defines the requirements for instances of CIM_AggregationMetricDefinition used to define high watermark metrics. These constraints are in addition to those specified in 10.1.

Table 22 – Class: CIM_AggregationMetricDefinition (High Watermark)

Properties	Requirement	Notes
SimpleFunction	Mandatory	Matches 3 (Maximum)

10.4 CIM_AggregationMetricValue

1123

1130

1124 CIM_AggregationMetricValue conveys the actual recorded data of a metric that has been maintained.

Table 23 describes the requirements for instances of CIM_AggregationMetricValue.

1126 Table 23 – Class: CIM_AggregationMetricValue

Properties	Requirement	Notes
MetricDefinitionId	Mandatory	None
MetricValue	Mandatory	None
Volatile	Mandatory	None
InstanceID	Mandatory	Key
BreakdownDimension	Optional	None
BreakdownValue	Optional	None
AggregationTimeStamp	Mandatory	None
AggregationDuration	Mandatory	None

1127 **10.5 CIM_BaseMetricDefinition**

1128 CIM_BaseMetricDefinition defines a metric that can be captured. Table 24 defines the requirements for instances of CIM_BaseMetricDefinition. This class is used as a basis for 10.6 to 10.10.

Table 24 - Class: CIM_BaseMetricDefinition

Properties	Requirement	Notes
BreakdownDimensions	Optional	See 7.1.4.
Calculatable	Optional	None
ChangeType	Mandatory	None
DataType	Mandatory	None
ElementName	Mandatory	Pattern (".+")
GatheringType	Mandatory	See 7.1.5.
ld	Mandatory	Key
IsContinuous	Optional	None
TimeScope	Optional	None
ProgrammaticUnits	Mandatory	None
Name	Mandatory	See 7.1.3.

1131 **10.6 CIM BaseMetricDefinition — Instantaneous Metric**

1132 Table 25 describes the requirements for using CIM_BaseMetricDefinition to define an Instantaneous

1133 Metric. These constraints are in addition to those specified in 10.5.

Table 25 – Class: CIM_BaseMetricDefinition – Instantaneous Metric

Properties	Requirement	Notes
IsContinuous	Mandatory	Matches TRUE
TimeScope	Mandatory	Matches 2 (Point)

1135 **10.7 CIM_BaseMetricDefinition** — Interval Metric

- 1136 Table 26 describes the requirements for using CIM_BaseMetricDefinition to define an Interval Metric.
- 1137 These constraints are in addition to those specified in 10.5.

1134

1143

1138 Table 26 – Class: CIM BaseMetricDefinition – Interval Metric

Properties	Requirement	Notes
TimeScope	Mandatory	Matches 3 (Interval)

1139 **10.8 CIM_BaseMetricDefinition** — Startup Interval Metric

1140 Table 27 describes the requirements for using CIM_BaseMetricDefinition to define a Startup Interval

1141 Metric. These constraints are in addition to those specified in 10.5.

1142 Table 27 – Class: CIM_BaseMetricDefinition – Startup Interval Metric

Properties	Requirement	Notes
TimeScope	Mandatory	Matches 4 (Startup Interval)

10.9 CIM_BaseMetricDefinition — Summation Metric

- 1144 Table 28 describes the requirements for using CIM_BaseMetricDefinition to define a Summation Metric.
- 1145 These constraints are in addition to those specified in 10.5.

1146 Table 28 – Class: CIM_BaseMetricDefinition – Summation Metric

Properties	Requirement	Notes
ChangeType	Mandatory	Matches 3 (Counter)
DataType	Mandatory	Matches 4 (real32), 5 (real64), 6 (sint16), 7 (sint32), 8 (sint64), 9 (sint8), 11 (unit16), 12 (uint32), 13 (uint64), or 14 (uint8)

1147 10.10 CIM BaseMetricDefinition — Current Data

Table 29 describes the requirements for using CIM_BaseMetricDefinition to define the metric to be used with current data. These constraints are in addition to those specified in 10.5.

Table 29 – Class: CIM_BaseMetricDefinition – Current Data

Properties	Requirement	Notes
TimeScope	Mandatory	Matches 2 (Point) or 3 (Interval)

1151 10.11 CIM BaseMetricValue

CIM_BaseMetricValue conveys the actual recorded data of a metric. Table 30 describes the requirements for instances of CIM_BaseMetricValue. This class is used as a basis for 10.12 to 10.16.

11531154

1156

1157

1158 1159

1160

1152

1150

1155

Table 30 - Class: CIM_BaseMetricValue

Properties	Requirement	Notes
MetricDefinitionId	Mandatory	None
MetricValue	Mandatory	None
Volatile	Mandatory	None
InstanceID	Mandatory	Key
BreakdownDimension	Optional	See 7.1.4.
BreakdownValue	Optional	See 7.1.4.
Timestamp	Optional	None
Duration	Optional	None

10.12 CIM_BaseMetricValue — Current Data

CIM_BaseMetricValue reports a metric defined using CIM_BaseMetricDefinition. Table 31 describes the requirements for using CIM_BaseMetricValue to report the metric for current data. These constraints are in addition to those specified in 10.11.

Table 31 - Class: CIM_BaseMetricValue - Current Data

Properties	Requirement	Notes
Timestamp	Mandatory	None
Volatile	Mandatory	Matches TRUE

1161 10.13 CIM_BaseMetricValue — Interval Metrics

1162 CIM_BaseMetricValue reports a metric defined using CIM_BaseMetricDefinition. Table 32 describes the requirements for using CIM_BaseMetricValue to report the metric for interval metrics. These constraints

are in addition to those specified in 10.11.

1165

1170

1175

1180

Table 32 - Class: CIM BaseMetricValue - Interval Metrics

Properties	Requirement	Notes
Duration	Mandatory	None
Timestamp	Mandatory	None

1166 10.14 CIM_BaseMetricValue — Startup Interval Metrics

1167 CIM_BaseMetricValue reports a metric defined using CIM_BaseMetricDefinition. Table 33 describes the requirements for using CIM_BaseMetricValue to report the metric for startup interval metrics. These constraints are in addition to those specified in 10.11.

Table 33 – Class: CIM_BaseMetricValue – Startup Interval Metrics

Properties	Requirement	Notes
Duration	Mandatory	None
Timestamp	Mandatory	None

1171 10.15 CIM BaseMetricValue — Summation Metric

1172 CIM_BaseMetricValue reports a metric defined using CIM_BaseMetricDefinition. Table 34 describes the requirements for using CIM_BaseMetricValue to report the metric for a Summation Metric. These constraints are in addition to those specified in 10.11.

Table 34 – Class: CIM BaseMetricValue – Summation Metric

Properties	Requirement	Notes
Timestamp	Mandatory	None

1176 **10.16 CIM_BaseMetricValue — Long-Term Monitoring**

1177 CIM_BaseMetricValue reports a metric defined using CIM_BaseMetricDefinition. Table 35 describes the requirements for using CIM_BaseMetricValue to report a metric for long-term monitoring. These constraints are in addition to those specified in 10.11.

Table 35 – Class: CIM_BaseMetricValue – Long-Term Monitoring

Properties	Requirement	Notes
Volatile	Mandatory	Matches FALSE

10.17 CIM_ConcreteDependency (Definition)

1181

1183

1182 Table 36 details the requirements for instances of CIM_ConcreteDependency.

Table 36 – Class: CIM_ConcreteDependency (Definition)

Elements	Requirement	Notes
Antecedent	Mandatory	Key: This property shall be a reference to CIM_BaseMetricDefinition.
		Cardinality 01
Dependent	Mandatory	Key: This property shall be a reference to CIM_AggregationMetricDefinition.
		Cardinality 01

1184 10.18 CIM_ConcreteDependency (Value)

1185 Table 37 details the requirements for instances of CIM_ConcreteDependency.

1186 Table 37 – Class: CIM_ConcreteDependency (Value)

Elements	Requirement	Notes
Antecedent	Mandatory	Key: This property shall be a reference to CIM_BaseMetricValue.
		Cardinality 01
Dependent	Mandatory	Key: This property shall be a reference to CIM_AggregationMetricValue.
		Cardinality 01

1187 10.19 CIM_ElementCapabilities

1188 CIM_ElementCapabilities associates an instance of CIM_MetricServiceCapabilities with the Central Instance. Table 38 details the requirements for instances of CIM_ElementCapabilities.

1190 Table 38 – Class: CIM_ElementCapabilities

Elements	Requirement	Notes
ManagedElement	Mandatory	Key: This property shall be a reference to the Central Instance.
		Cardinality 1
Capabilities	Mandatory	Key: This property shall be a reference to an instance of CIM_MetricServiceCapabilities.
		Cardinality 1

10.20 CIM_HostedService

1191

1202

1192 Table 39 details the requirements for instances of CIM_HostedService.

1193 Table 39 – Class: CIM HostedService

Elements	Requirement	Notes
Antecedent	Mandatory	Key: This property shall be a reference to the Scoping Instance.
		Cardinality 1
Dependent	Mandatory	Key: This property shall be a reference to the Central Instance.
		Cardinality 1*

1194 **10.21 CIM MetricDefForME**

1195 CIM_MetricForME relates a metric to the managed element for which it was measured. Table 40 details the requirements for instances of CIM_MetricDefForME.

1197 Table 40 – Class: CIM_MetricDefForME

Properties	Requirement	Notes
Antecedent	Mandatory	Cardinality 1*
Dependent	Mandatory	Cardinality *
MetricCollectionEnabled	Mandatory	None

1198 **10.22 CIM_MetricForME**

1199 CIM_MetricForME relates a metric to the managed element for which it was measured. Table 41 details the requirements for instances of CIM_MetricForME.

1201 Table 41 – Class: CIM MetricForME

Properties	Requirement	Notes
Antecedent	Mandatory	Cardinality 1*
Dependent	Mandatory	Cardinality *

10.23 CIM_MetricInstance

1203 CIM_MetricInstance relates a CIM_BaseMetricValue to the CIM_BaseMetricDefinition that defines it.
1204 Table 42 details the requirements for instances of CIM_MetricInstance.

1205 Table 42 – Class: CIM MetricInstance

Properties	Requirement	Notes
Antecedent	Mandatory	See 7.1.2.
		Cardinality 1
Dependent	Mandatory	See 7.1.2.
		Cardinality *

10.24 CIM_MetricService

1206

1209

1213

1207 Table 43 details the requirements for instances of CIM_MetricService.

1208 Table 43 – Class: CIM_MetricService

Elements	Requirement	Notes
SystemCreationClassName	Mandatory	Key
CreationClassName	Mandatory	Key
SystemName	Mandatory	Key
Name	Mandatory	Key
ElementName	Mandatory	Pattern ".*"
ShowMetrics()	Conditional	See 8.1.
ShowMetricsByClass()	Conditional	See 8.2.
ControlMetrics()	Conditional	See 8.3.
ControlMetricsByClass()	Conditional	See 8.4.
GetMetricValues()	Conditional	See 8.5.

10.25 CIM_MetricServiceCapabilities

1210 CIM_MetricServiceCapabilities indicates support for managing the state of the service as well as the accounts with which the service is associated. Table 44 details the requirements for instances of CIM_MetricServiceCapabilities.

Table 44 – Class: CIM_MetricServiceCapabilities

Elements	Requirement	Notes
InstanceID	Mandatory	None
ElementName	Mandatory	Pattern ".*"
SupportedMethods	Mandatory	None
ControllableMetrics	Mandatory	None
MetricControlTypes	Mandatory	None
ControllableManagedElements	Mandatory	None
ManagedElementControlTypes	Mandatory	None

10.26 CIM_RegisteredProfile

1215 CIM_RegisteredProfile identifies the Base Metrics Profile. The CIM_RegisteredProfile class is defined by

the Profile Registration Profile. With the exception of the mandatory values specified for the properties in 1216

Table 45, the behavior of the CIM RegisteredProfile instance is in accordance with the constraints 1217

1218 specified in the Profile Registration Profile.

Table 45 - Class: CIM_RegisteredProfile

Properties Requirement Notes		Notes
RegisteredName	Mandatory	This property shall have a value of "Base Metrics".
RegisteredVersion	Mandatory	This property shall have a value of "1.0.1".
RegisteredOrganization	Mandatory	This property shall have a value of 2 (DMTF).

10.27 CIM_ServiceAffectsElement

1221 CIM_ServiceAffectsElement is used to associate an instance of CIM_MetricService with an instance of CIM_BaseMetricDefinition or CIM_AggregationMetricDefinition that represents a metric that could be 1222 controlled using the service. Table 46 contains the requirements for elements of this class. 1223

1224

Table 46 - Class: CIM_ServiceAffectsElement

Elements	Requirement	Notes
AffectedElement	Mandatory	Key : This property shall reference the instance of CIM_BaseMetricDefinition or CIM_AggregationMetricDefinition.
		Cardinality 1*
AffectingElement	Mandatory	Key : This property shall reference the instance of CIM_MetricService.
		Cardinality 1
ElementAffects	Mandatory	Matches 5 (Manages)

1225

1214

1219

1226 1227 (Informative) 1228 1229

Change Log

Version	Date	Description	
1.0.0	2009-06-16	DMTF Standard	
1.0.1	2009-12-11	DMTF Standard, with the following changes:	
		 Corrected inconsistencies based on the published profiles incorporating metric definitions and DSP0004 programmatic unit definitions. 	

1231

1232	ANNEX B								
1233	(Informative)								
1234	Outide for Occurrent Matrice								
1235	Guide for Common Metrics								
1236 1237 1238 1239 1240 1241 1242	This annex provides an informative list of the combined mandatory properties for instances of CIM_BaseMetricDefinition, CIM_AggregationMetricDefinition, CIM_BaseMetricValue, and CIM_AggregationMetricValue if used to represent common metrics. Each of the data cells of the tables lists mandatory properties and their value formulations for a specific type of metric. Each table corresponds to a different type of metrics grouped by value formulation. The rows represent the different type of metrics based on the time scope that metric describes. The columns describe the different type of metrics based on the metric collection access type used.								
1243 1244	In order to determine the mandatory set of properties, match the type of metric to one of the data cells based on the metric's value formulation, time scope, and collection access type.								
1245	The following conventions are used in the table:								
1246	BMD – the properties that follow are required on the instance of CIM_BaseMetricDefinition								
1247	BMV – the properties that follow are required on the instance of CIM_BaseMetricValue								
1248 1249	 AMD – the propertiest that follow are required on the instance of CIM_AggregationMetricDefinition 								
1250	AMV – the properties that follow are required on the instance of CIM_AggregationMetricValue								
1251	A property name without a value specified is required, and the value is not fixed.								
1252	 A property name followed by a value assignment is required with the specified value fixed. 								
1253 1254 1255	NOTE: If there is a mismatch between the mandatory set of properties and/or the properties' value formulation indicated by the tables in this annex and the requirements detailed in clauses 7 and 10, the requirements mandated in clauses 7 and 10 take precedence.								
1256	B.1 Simple Metric								
1257 1258	Table B.1 describes the mandatory properties for simple metric as described in 6.3.1 according to the appropriate metric access type and time scope.								

Table B.1 – Simple Metric

	Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
	BMD	BMD	BMD	BMD	BMD
	ChangeType	ChangeType	ChangeType	ChangeType	ChangeType
	DataType	DataType	DataType	DataType	DataType
Instantaneous Metrics	ElementName	ElementName	ElementName	ElementName	ElementName
	GatheringType Id IsContinuous = TRUE TimeScope = 2 (Point) ProgrammaticUnits Name	GatheringType = 3 (Periodic) or 2 (OnChange) Id IsContinuous = TRUE TimeScope = 2 (Point) ProgrammaticUnits Name	GatheringType = 4 (OnRequest) Id IsContinuous = TRUE TimeScope = 2 (Point) ProgrammaticUnits Name	GatheringType Id IsContinuous = TRUE TimeScope = 2 (Point) ProgrammaticUnits Name	GatheringType Id IsContinuous = TRUE TimeScope = 2 (Point) ProgrammaticUnits Name
Inst			5.57	5.07	510/
	BMV	BMV	BMV	BMV	BMV
	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
	MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
	Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
	InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
	Duration	Duration	Duration		
	Timestamp	Timestamp	Timestamp	DMD	DMD
	BMD	BMD	BMD	BMD	BMD
	ChangeType	ChangeType	ChangeType	ChangeType	ChangeType
	DataType ElementName	DataType ElementName	DataType ElementName	DataType ElementName	DataType ElementName
	GatheringType	GatheringType = 3	GatheringType = 4	GatheringType	GatheringType
	ld	(Periodic) or 2	(OnRequest)	Id	Id
Interval Metrics	TimeScope = 3 (Interval) ProgrammaticUnits Name	(OnChange) Id TimeScope = 3 (Interval) ProgrammaticUnits Name	Id TimeScope = 3 (Interval) ProgrammaticUnits Name	TimeScope = 3 (Interval) ProgrammaticUnits Name	TimeScope = 3 (Interval) ProgrammaticUnits Name
=	BMV	BMV	BMV	BMV	BMV
	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
	MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
	Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
	InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
	Duration	Duration	Duration	Duration	Duration
	Timestamp	Timestamp	Timestamp	Timestamp	Timestamp

	Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
	BMD	BMD	BMD	BMD	BMD
	ChangeType	ChangeType	ChangeType	ChangeType	ChangeType
	DataType	DataType	DataType	DataType	DataType
	ElementName	ElementName	ElementName	ElementName	ElementName
	GatheringType	GatheringType = 3	GatheringType = 4	GatheringType	GatheringType
	ld	(Periodic) or 2 (OnChange)	(OnRequest)	ld	ld
Startup Metrics	TimeScope = 4 (StartupInterval) ProgrammaticUnits Name	Id TimeScope = 4 (StartupInterval) ProgrammaticUnits Name	Id TimeScope = 4 (StartupInterval) ProgrammaticUnits Name	TimeScope = 4 (StartupInterval) ProgrammaticUnits Name	TimeScope = 4 (StartupInterval) ProgrammaticUnits Name
Ó	BMV	BMV	BMV	BMV	вму
	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
	MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
	Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
	InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
	Duration	Duration	Duration	Duration	Duration
	Timestamp	Timestamp	Timestamp	Timestamp	Timestamp

B.2 Summation Metric

1260

1261 1262 Table B.2 describes the mandatory properties for summation metric as described in 6.3.2 according to the appropriate metric access type and time scope.

1263 Table B.2 – Summation Metric

	Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
	BMD	BMD	BMD	BMD	BMD
	ChangeType = 3 (Counter)				
	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)
ics	ElementName	ElementName	ElementName	ElementName	ElementName
/letr	GatheringType	GatheringType = 3	GatheringType = 4	GatheringType	GatheringType
l sn	ld	(Periodic) or 2 (OnChange)	(OnRequest)	Id	ld
aneol	IsContinuous = TRUE	Id	Id IsContinuous =	IsContinuous = TRUE	IsContinuous = TRUE
Instantaneous Metrics	TimeScope = 2 (Point) ProgrammaticUnits	IsContinuous = TRUE TimeScope = 2	TRUE TimeScope = 2 (Point)	TimeScope = 2 (Point) ProgrammaticUnits	TimeScope = 2 (Point) ProgrammaticUnits
	Name	(Point) ProgrammaticUnits	ProgrammaticUnits Name	Name	Name
		Name			
	BMV	BMV	BMV	BMV	BMV
	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
	MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
	Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
	InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
	Timestamp	Timestamp	Timestamp		

		Current Data –	Current Data – Snapshot	Long-Term	Event-Based
	Current Data	Online Monitoring	Monitoring	Monitoring	Monitoring
	BMD	BMD	BMD	BMD	BMD
	ChangeType = 3 (Counter)				
	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)
SS	ElementName	ElementName	ElementName	ElementName	ElementName
Interval Metrics	GatheringType Id	GatheringType = 3 (Periodic) or 2 (OnChange)	GatheringType = 4 (OnRequest)	GatheringType Id	GatheringType Id
Interva	TimeScope = 3 (Interval) ProgrammaticUnits Name	Id TimeScope = 3 (Interval) ProgrammaticUnits	Id TimeScope = 3 (Interval) ProgrammaticUnits Name	TimeScope = 3 (Interval) ProgrammaticUnits Name	TimeScope = 3 (Interval) ProgrammaticUnits Name
	DMV	Name BMV	DMV	DMV/	BMV
	BMV MetricDefinitionId	MetricDefinitionId	BMV MetricDefinitionId	BMV MetricDefinitionId	MetricDefinitionId
	MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
	Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
	InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
	Timestamp	Timestamp	Timestamp	Timestamp	Timestamp
	BMD	BMD	BMD	BMD	BMD
	ChangeType = 3 (Counter)	ChangeType = 3 (Counter)			
Startup Metrics	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)	DataType = 4 (real32) or 5 (real64) or 6 (sint16) or 7 (sint32) or 8 (sint64) or 9 (sint8) or 11 (unit16) or 12 (uint32) or 13 (uint64) or 14 (uint8)
artu	ElementName	ElementName	ElementName	ElementName	ElementName
Ş	GatheringType Id	GatheringType = 3 (Periodic) or 2 (OnChange)	GatheringType = 4 (OnRequest)	GatheringType Id	GatheringType Id
	TimeScope = 4 (StartupInterval) ProgrammaticUnits Name	Id TimeScope = 4 (StartupInterval) ProgrammaticUnits Name	Id TimeScope = 4 (StartupInterval) ProgrammaticUnits Name	TimeScope = 4 (StartupInterval) ProgrammaticUnits Name	TimeScope = 4 (StartupInterval) ProgrammaticUnits Name

Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
BMV	BMV	BMV	BMV	BMV
MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
Timestamp	Timestamp	Timestamp	Timestamp	Timestamp

B.3 Aggregation Metric

1264

1265 1266

1267

Table B.3 describes the mandatory properties for aggregation metric as described in section 6.3.3 according to the appropriate metric access type and time scope.

Table B.3 – Aggregation Metric

	Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
	AMD	AMD	AMD	AMD	AMD
	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)
	DataType	DataType	DataType	DataType	DataType
	ElementName	ElementName	ElementName	ElementName	ElementName
Instantaneous Metrics	GatheringType Id IsContinuous = TRUE TimeScope = 2 (Point) ProgrammaticUnits Name SimpleFunction	GatheringType = 3 (Periodic) or 2 (OnChange) Id IsContinuous = TRUE TimeScope = 2 (Point) ProgrammaticUnits Name SimpleFunction	GatheringType = 4 (OnRequest) Id IsContinuous = TRUE TimeScope = 2 (Point) ProgrammaticUnits Name SimpleFunction	GatheringType Id IsContinuous = TRUE TimeScope = 2 (Point) ProgrammaticUnits Name SimpleFunction	GatheringType Id IsContinuous = TRUE TimeScope = 2 (Point) ProgrammaticUnits Name SimpleFunction
nsta	AMV	AMV	AMV	AMV	AMV
	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
	MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
	Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
	InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
	Duration	Duration	Duration	AggregationTime- Stamp	AggregationTime- Stamp
	Timestamp AggregationTime- Stamp	Timestamp AggregationTime- Stamp	Timestamp AggregationTime- Stamp	AggregationDuration	AggregationDuration
	AggregationDuration	AggregationDuration	AggregationDuration		

Version 1.0.1 DMTF Standard 63

	Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
	AMD	AMD	AMD	AMD	AMD
	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)
	DataType	DataType	DataType	DataType	DataType
	ElementName	ElementName	ElementName	ElementName	ElementName
	GatheringType Id	GatheringType = 3 (Periodic) or 2	GatheringType = 4 (OnRequest)	GatheringType Id	GatheringType Id
ý	TimeScope = 3 (Interval) ProgrammaticUnits	(OnChange) Id TimeScope = 3	Id TimeScope = 3 (Interval)	TimeScope = 3 (Interval) ProgrammaticUnits	TimeScope = 3 (Interval) ProgrammaticUnits
tric	Name	(Interval) ProgrammaticUnits	ProgrammaticUnits	Name	Name
Interval Metrics	SimpleFunction	Name SimpleFunction	Name SimpleFunction	SimpleFunction	SimpleFunction
nter	AMV	AMV	AMV	AMV	AMV
_	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
	MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
	Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
	InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
	Duration	Duration	Duration	Duration	Duration
	Timestamp	Timestamp	Timestamp	Timestamp	Timestamp
	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp
	AggregationDuration	AggregationDuration	AggregationDuration	AggregationDuration	AggregationDuration
	AMD	AMD	AMD	AMD	AMD
	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)
	DataType	DataType	DataType	DataType	DataType
S	ElementName	ElementName	ElementName	ElementName	ElementName
Metrics	GatheringType	GatheringType = 3	GatheringType = 4	GatheringType	GatheringType
	ld	(Periodic) or 2 (OnChange)	(OnRequest)	ld	ld
Startup	TimeScope = 4 (StartupInterval) ProgrammaticUnits	Id TimeScope = 4	TimeScope = 4 (StartupInterval)	TimeScope = 4 (StartupInterval) ProgrammaticUnits	TimeScope = 4 (StartupInterval) ProgrammaticUnits
	Name	(StartupInterval)	ProgrammaticUnits	Name	Name
	SimpleFunction	ProgrammaticUnits	Name	SimpleFunction	SimpleFunction
	Cimpler directori	Name	SimpleFunction	Cimpler diletion	Cimpion direction
		SimpleFunction			

Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
AMV	AMV	AMV	AMV	AMV
MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
Duration	Duration	Duration	Duration	Duration
Timestamp	Timestamp	Timestamp	Timestamp	Timestamp
AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp
AggregationDuration	AggregationDuration	AggregationDuration	AggregationDuration	AggregationDuration

B.4 Aggregation Metric — Low Watermark

1268

1269 1270

1271

Table B.4 describes the mandatory properties for low watermark as a type of an aggregation metric as described in section 6.3.3.1 according to the appropriate metric access type and time scope.

Table B.4 – Aggregation Metric – Low Watermark

	Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
	AMD	AMD	AMD	AMD	AMD
	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)
	DataType	DataType	DataType	DataType	DataType
Ø	ElementName	ElementName	ElementName	ElementName	ElementName
Metrics	GatheringType	GatheringType = 3 (Periodic) or 2 (OnChange) Id IsContinuous = TRUE TimeScope = 2 (Point) ProgrammaticUnits	(OnRequest) Id IsContinuous = TRUE TimeScope = 2 (Point) ProgrammaticUnits	GatheringType	GatheringType
	Id			Id	Id
Instantaneous	IsContinuous = TRUE			IsContinuous = TRUE	IsContinuous = TRUE
tantaı	TimeScope = 2 (Point)			TimeScope = 2 (Point)	TimeScope = 2 (Point)
lus	ProgrammaticUnits			ProgrammaticUnits	ProgrammaticUnits
	Name			Name	Name
	SimpleFunction = 2 (Minimum)	Name SimpleFunction = 2 (Minimum)	Name SimpleFunction = 2 (Minimum)	SimpleFunction = 2 (Minimum)	SimpleFunction = 2 (Minimum)

	Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
	AMV	AMV	AMV	AMV	AMV
	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
	MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
	Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
	InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
	Duration	Duration	Duration	AggregationTime-	AggregationTime-
	Timestamp	Timestamp	Timestamp	Stamp	Stamp
	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationDuration	AggregationDuration
	AggregationDuration	AggregationDuration	AggregationDuration		
	AMD	AMD	AMD	AMD	AMD
	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)
	DataType	DataType	DataType	DataType	DataType
	ElementName	ElementName	ElementName	ElementName	ElementName
	GatheringType	GatheringType = 3	GatheringType = 4	GatheringType	GatheringType
	Id	(Periodic) or 2 (OnChange)	(OnRequest)	ld	Id
	TimeScope = 3	Id	ld Time Cooks of	TimeScope = 3	TimeScope = 3
	(Interval) ProgrammaticUnits	TimeScope = 3	TimeScope = 3 (Interval)	(Interval) ProgrammaticUnits	(Interval) ProgrammaticUnits
SS	Name	(Interval)	ProgrammaticUnits	Name	Name
etri	SimpleFunction = 2	ProgrammaticUnits	Name	SimpleFunction = 2	SimpleFunction = 2
≥	(Minimum)	Name	SimpleFunction = 2	(Minimum)	(Minimum)
Interval Metrics		SimpleFunction = 2 (Minimum)	(Minimum)		
重	AMV	AMV	AMV	AMV	AMV
	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
	MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
	Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
	InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
	Duration	Duration	Duration	Duration	Duration
	Timestamp	Timestamp	Timestamp	Timestamp	Timestamp
	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp
	AggregationDuration	AggregationDuration	AggregationDuration	AggregationDuration	AggregationDuration

	Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
	AMD	AMD	AMD	AMD	AMD
	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)
	DataType	DataType	DataType	DataType	DataType
	ElementName	ElementName	ElementName	ElementName	ElementName
	GatheringType	GatheringType = 3	GatheringType = 4	GatheringType	GatheringType
	Id	(Periodic) or 2 (OnChange)	(OnRequest)	ld	Id
	TimeScope = 4 (StartupInterval) ProgrammaticUnits	Id TimeScope = 4	Id TimeScope = 4 (StartupInterval)	TimeScope = 4 (StartupInterval) ProgrammaticUnits	TimeScope = 4 (StartupInterval) ProgrammaticUnits
<u>S</u>	Name	(StartupInterval) ProgrammaticUnits	ProgrammaticUnits	Name	Name
Startup Metrics	SimpleFunction = 2 (Minimum)	Name SimpleFunction = 2 (Minimum)	Name SimpleFunction = 2 (Minimum)	SimpleFunction = 2 (Minimum)	SimpleFunction = 2 (Minimum)
S	AMV	AMV	AMV	AMV	AMV
	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
	MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
	Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
	InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
	Duration	Duration	Duration	Duration	Duration
	Timestamp	Timestamp	Timestamp	Timestamp	Timestamp
	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp
	AggregationDuration	AggregationDuration	AggregationDuration	AggregationDuration	AggregationDuration

B.5 Aggregation Metric — High Watermark

1272

1273 1274

1275

Table B.5 describes the mandatory properties for high watermark as a type of an aggregation metric as described in section 6.3.3.1 according to the appropriate metric access type and time scope.

Table B.5 – Aggregation Metric – High Watermark

	Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
	AMD	AMD	AMD	AMD	AMD
	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)
	DataType	DataType	DataType	DataType	DataType
	ElementName	ElementName	ElementName	ElementName	ElementName
	GatheringType	GatheringType = 3	GatheringType = 4	GatheringType	GatheringType
	Id	(Periodic) or 2 (OnChange)	(OnRequest)	Id	ld
	IsContinuous = TRUE	ld	Id IsContinuous =	IsContinuous = TRUE	IsContinuous = TRUE
Metrics	TimeScope = 2 (Point) ProgrammaticUnits Name	IsContinuous = TRUE TimeScope = 2 (Point)	TRUE TimeScope = 2 (Point) ProgrammaticUnits	TimeScope = 2 (Point) ProgrammaticUnits Name	TimeScope = 2 (Point) ProgrammaticUnits Name
Instantaneous Metrics	SimpleFunction = 3 (Maximum)	ProgrammaticUnits Name SimpleFunction = 3 (Maximum)	Name SimpleFunction = 3 (Maximum)	SimpleFunction = 3 (Maximum)	SimpleFunction = 3 (Maximum)
lus	AMV	AMV	AMV	AMV	AMV
	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
	MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
	Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
	InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
	Duration	Duration	Duration	AggregationTime-	AggregationTime-
	Timestamp	Timestamp	Timestamp	Stamp	Stamp
	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationDuration	AggregationDuration
	AggregationDuration	AggregationDuration	AggregationDuration		

	Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
	AMD	AMD	AMD	AMD	AMD
	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)
	DataType	DataType	DataType	DataType	DataType
	ElementName	ElementName	ElementName	ElementName	ElementName
	GatheringType	GatheringType = 3	GatheringType = 4	GatheringType	GatheringType
	ld	(Periodic) or 2 (OnChange)	(OnRequest)	Id	Id
	TimeScope = 3 (Interval)	Id	ld	TimeScope = 3	TimeScope = 3
	ProgrammaticUnits	TimeScope = 3	TimeScope = 3 (Interval)	(Interval) ProgrammaticUnits	(Interval) ProgrammaticUnits
S	Name	(Interval)	ProgrammaticUnits	Name	Name
etri	SimpleFunction = 3	ProgrammaticUnits	Name	SimpleFunction = 3	SimpleFunction = 3
Ž	(Maximum)	Name	SimpleFunction = 3	(Maximum)	(Maximum)
Interval Metrics		SimpleFunction = 3 (Maximum)	(Maximum)		
<u> =</u>	AMV	AMV	AMV	AMV	AMV
	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
	MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
	Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
	InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
	Duration	Duration	Duration	Duration	Duration
	Timestamp	Timestamp	Timestamp	Timestamp	Timestamp
	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp
	AggregationDuration	AggregationDuration	AggregationDuration	AggregationDuration	AggregationDuration
	AMD	AMD	AMD	AMD	AMD
	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)	ChangeType = 5 (Simple Function)
	DataType	DataType	DataType	DataType	DataType
y,	ElementName	ElementName	ElementName	ElementName	ElementName
etrics	GatheringType	GatheringType = 3	GatheringType = 4	GatheringType	GatheringType
Startup Met	ld TimeSeene 4	(Periodic) or 2 (OnChange)	(OnRequest)	ld	ld
	TimeScope = 4 (StartupInterval)	Id	Id TimeScope = 4	TimeScope = 4 (StartupInterval)	TimeScope = 4 (StartupInterval)
	ProgrammaticUnits	TimeScope = 4	(StartupInterval)	ProgrammaticUnits	ProgrammaticUnits
	Name	(StartupInterval)	ProgrammaticUnits	Name	Name
	SimpleFunction = 3	ProgrammaticUnits	Name	SimpleFunction = 3	SimpleFunction = 3
	(Maximum)	Name SimpleFunction = 3	SimpleFunction = 3	(Maximum)	(Maximum)
		(Maximum)	(Maximum)		

Current Data	Current Data – Online Monitoring	Current Data – Snapshot Monitoring	Long-Term Monitoring	Event-Based Monitoring
AMV	AMV	AMV	AMV	AMV
MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId	MetricDefinitionId
MetricValue	MetricValue	MetricValue	MetricValue	MetricValue
Volatile = TRUE	Volatile = TRUE	Volatile = TRUE	Volatile = FALSE	Volatile
InstanceID	InstanceID	InstanceID	InstanceID	InstanceID
Duration	Duration	Duration	Duration	Duration
Timestamp	Timestamp	Timestamp	Timestamp	Timestamp
AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp	AggregationTime- Stamp
AggregationDuration	AggregationDuration	AggregationDuration	AggregationDuration	AggregationDuration

1276

1278 Bibliography

1279 DMTF DSP1073, Capacity Metrics Profile 1.0